

erwin Data Intelligence

Reference Data Management Guide

Release v15.0

Legal Notices

This Documentation, which includes embedded help systems and electronically distributed materials (hereinafter referred to as the Documentation), is for your informational purposes only and is subject to change or withdrawal by Quest Software, Inc and/or its affiliates at any time. This Documentation is proprietary information of Quest Software, Inc and/or its affiliates and may not be copied, transferred, reproduced, disclosed, modified or duplicated, in whole or in part, without the prior written consent of Quest Software, Inc and/or its affiliates

If you are a licensed user of the software product(s) addressed in the Documentation, you may print or otherwise make available a reasonable number of copies of the Documentation for internal use by you and your employees in connection with that software, provided that all Quest Software, Inc and/or its affiliates copyright notices and legends are affixed to each reproduced copy.

The right to print or otherwise make available copies of the Documentation is limited to the period during which the applicable license for such software remains in full force and effect. Should the license terminate for any reason, it is your responsibility to certify in writing to Quest Software, Inc and/or its affiliates that all copies and partial copies of the Documentation have been returned to Quest Software, Inc and/or its affiliates or destroyed.

TO THE EXTENT PERMITTED BY APPLICABLE LAW, QUEST SOFTWARE, INC. PROVIDES THIS DOCUMENTATION AS IS WITHOUT WARRANTY OF ANY KIND, INCLUDING WITHOUT LIMITATION, ANY IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NONINFRINGEMENT. IN NO EVENT WILL QUEST SOFTWARE, INC. BE LIABLE TO YOU OR ANY THIRD PARTY FOR ANY LOSS OR DAMAGE, DIRECT OR INDIRECT, FROM THE USE OF THIS DOCUMENTATION, INCLUDING WITHOUT LIMITATION, LOST PROFITS, LOST INVESTMENT, BUSINESS INTERRUPTION, GOODWILL, OR LOST DATA, EVEN IF QUEST SOFTWARE, INC. IS EXPRESSLY ADVISED IN ADVANCE OF THE POSSIBILITY OF SUCH LOSS OR DAMAGE.

The use of any software product referenced in the Documentation is governed by the applicable license agreement and such license agreement is not modified in any way by the terms of this notice.

The manufacturer of this Documentation is Quest Software, Inc and/or its affiliates Provided with Restricted Rights. Use, duplication or disclosure by the United States Government is subject to the restrictions set forth in FAR Sections 12.212, 52.227-14, and 52.227-19(c)(1) - (2) and DFARS Section 252.227-7014(b)(3), as applicable, or their successors.

Copyright © Quest Software, Inc. and/or its affiliates All rights reserved. All trademarks, trade names, service marks, and logos referenced herein belong to their respective companies.

Contact erwin

Understanding your Support

Review support maintenance programs and offerings.

Registering for Support

Access the erwin support site and click Sign in to register for product support.

Accessing Technical Support

For your convenience, erwin provides easy access to "One Stop" support for <u>erwin Data</u> <u>Intelligence (erwin DI)</u>, and includes the following:

- Online and telephone contact information for technical assistance and customer services
- Information about user communities and forums
- Product and documentation downloads
- erwin Support policies and guidelines
- Other helpful resources appropriate for your product

For information about other erwin products, visit http://erwin.com/.

Provide Feedback

If you have comments or questions, or feedback about erwin product documentation, you can send a message to distechpubs@erwin.com.

News and Events

Visit <u>News and Events</u> to get up-to-date news, announcements, and events. View video demos and read up on customer success stories and articles by industry experts.

Contents

Reference Data and Codeset Manager	7
Reference Data Manager	8
Creating Reference Folders	9
Managing Reference Folders	11
Creating Reference Tables	13
Importing Data from Spreadsheets	15
Adding Columns to Reference Tables	18
Adding Column Values Manually	21
Importing Column Values from MS Excel Files	23
Importing Column Values Through DB Scans	25
Managing Reference Tables	29
Creating Publish Environments	31
Adding Validation Rules	32
Associating Validation Rules with Reference Tables	35
Running Validations Against Reference Tables	37
Associating Codesets With Reference Tables	39
Versioning Reference Tables	41
Publishing Reference Tables	44
Associating Reference Tables with Mappings	48
Codeset Manager	50
Maintaining Enterprise Codesets	52
Creating Categories	53

Managing Categories	55
Assigning Users	57
Adding Codesets	59
Entering Codes Manually	61
Importing Codes using MS Excel Files	65
Importing Codes into Code Value Grid using DB Scan	67
Managing Codesets	72
Versioning Codesets	75
Deleting Codes and Codesets	77
Publishing Codesets	80
Maintaining Code Mappings	84
Creating Categories	85
Managing Categories	88
Creating Code Crosswalks (Mappings)	90
Creating Code Crosswalks - Source and Target Codesets with Same Code Value	90
Creating Code Crosswalks - Source and Target Codesets with Different Code Value	92
Editing Code Mappings	97
Versioning Code Mappings	100
Associating Code Maps with Data Item Mappings	102
Publishing Code Maps	102
Associating Code Maps	104

Reference Data and Codeset Manager

This section walks you through reference data and codeset management.

Reference data management is done via Reference Data Manager. It involves creating database like structures to maintain all your reference data. You can add reference data in a reference table from a spreadsheet, manually or via a DB scan. To validate reference tables for data quality tests, you can use SQL queries. You can also version, publish (to environments like production, development, test etc.), and link the reference tables to relevant mappings.


For further information on accessing and using the Reference Data Manager, refer to the Reference Data Manager topic.

- Codeset management is done via Codeset Manager. It involves creating, managing, and mapping codesets in the Codeset Manager. It has two sections:
 - Enterprise Codesets: Under the Enterprise Codesets section, you can create and manage codesets. It involves importing legacy codesets, categorizing codesets, defining code values, versioning codesets, and publishing codesets to various environments.
 - Codeset Mappings: Under the Codeset Mappings section, you can create and manage code crosswalks (mappings). It involves categorizing code mappings, defining code crosswalks, versioning code crosswalks, and publishing code crosswalks to various environments.

For further information on accessing and using the Codeset Manager, refer to the Codeset Manager topic.

Reference Data Manager

To access the Reference Data Manager, go to Application Menu > Data Catalog > Reference Data Manager. The Reference Data Manager dashboard appears:



UI Section	Function
1-Workspace	Use this pane to browse and work on validation rules, environments,
	reference folders, and reference tables.
2-Right Pane	Use this pane to work on the data based on your selection in the Work-
	space pane.
3-Additional Table	Use this pane to view or work on additional information of a reference
Information	table selected in the Workspace pane.
4-Published Tables	Use this pane to browse, view, and export published reference tables.

Managing reference data involves the following:


- Creating reference folders
- Creating reference tables
- Creating publish environments
- Adding validation rules
- Associating codesets with reference tables
- Versioning reference tables
- Publishing reference tables
- Associating reference tables with mappings

Creating Reference Folders

Reference folders group reference tables based on your data integration project. Therefore, before creating reference tables, you need to create a reference folder. You can also create sub-folders to group reference tables further.


To create reference folders, follow these steps:

- 1. Go to Application Menu > Data Catalog > Reference Data Manager.
- 2. In the Workspace pane, right-click the Reference Folders node.



3. Click New Folder.

The New Folder page appears.



4. Enter the Folder Name and Folder Description.

For example:

Folder Name: City Names

Folder Description: This folder contains reference tables for city names.

5. Click .

The folder is created and saved in the Reference Folders tree.

Once a reference folder is created, you can manage it using the options available on rightclicking the reference folder. Managing reference folders involves:

- Creating sub-folders
- Editing reference folders
- Assigning users
- Deleting reference folders


Managing Reference Folders

Managing reference folders involves:

- Creating sub-folders
- Editing reference folders
- Assigning users
- Deleting reference folders

To manage reference folders, follow these steps:

1. In the Workspace pane, right-click a reference folder.



2. Use the following options:

New Sub Folder

Use this option to create sub-folders and group reference tables further.

Edit Folder

Use this option to update reference folder's name and description.

Assign Users

Use this option to assign users to a reference folder based on project, departments, functions, and so on. On the Assign Users page, select user IDs under User ID list-box and move them to Assigned Users list-box using the arrows (or). Similarly, to change existing user assignment, select user IDs under Assigned Users list-box and move them back to User ID list-box using the arrows (or 1).

Delete


Use this option to delete a reference folder that is no more required.

Reference tables store reference data. You can create reference tables in new or existing reference folders. You can also create reference tables under the reference sub-folders.

To create reference tables, follow these steps:


- 1. Go to Application Menu > Data Catalog > Reference Data Manager.
- 2. In the Workspace pane, right-click a reference folder or sub-folder.

For example, if you right-click a reference folder the following options appear.



3. Click New Table.

The New Reference Table page appears.



4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description	
	Specifies the name of the reference folder.	
Folder Name For example, NASDAQ Healthcare.		
	It is autopopulated and cannot be edited.	
Table Name	Specifies the name of the reference table.	
Table Name	For example, Data_Classifications_Levels.	
	Specifies the version of the reference table.	
Version	For example, 1.00.	
	It is autopopulated and cannot be edited.	
Owner	Specifies the reference table owner's name.	
	For example, Talon Smith.	
Data Ste-	Specifies the name of the data steward responsible for the reference	

Field Name	Description
	table.
ward	For example, Jane Doe.
	Users assigned with the Legacy Data Steward role appear as drop down options. You can assign this role to a user in the Resource Manager.
	To assign data steward, select a data steward from the drop down
	options.
	Specifies the description about the reference table.
Description	For example: This reference table serves as domain for the data clas-
	sification column.
Import Data	Use this check box to import reference data into the reference table
from Spread-	from the XLSX file. For more information, refer to the Importing Data
sheet	<u>from Spreadsheets</u> section below.


5. Click

A reference table is created and saved in the Reference Tables tree.

Importing Data from Spreadsheets


To import reference data from MS Excel files, follow these steps:

1. On the New Reference Table page, click the Import Data from Spreadsheet check box.



- 2. Drag and drop or use = to browse and select the XLSX file.
- 3. Click Next.

The Preview Screen page appears. To exclude a column from the import process, double-click the column header and click NOT_IN_USE.



4. Click 1

The reference data is imported into the reference table.

If you do not click the Import Data from Spreadsheet check box, you need to add columns to the reference table and then add column values:

- Manually
- From MS Excel files
- Through DB scans

You can manage a reference table using the options available on right-clicking the reference table. Managing reference tables involves:


- · Altering reference tables
- Copying reference tables
- · Assigning users to reference tables
- Deleting reference tables

Adding Columns to Reference Tables

After creating a reference table, you can add columns to the reference table.

To add columns to reference tables, follow these steps:


1. In the **Workspace** pane, right-click a reference table.



2. Click Alter Table.

The Alter Table page appears.

Adding Columns to Reference Tables




3. Click •

A new row is added to the grid.

4. Double-click the cell under the **Column Name** and enter the column name.


You can add multiple columns.

Adding Columns to Reference Tables



5. Click

The columns are added to the reference table.



Once columns are added to a reference table, you can import column values:

- Manually
- From MS Excel files
- Through DB scans

Adding Column Values Manually

You can add data to a reference table manually. It involves adding columns to the reference table and then adding column values. For more information on adding columns to reference tables, refer to the Adding Columns to Reference Tables topic.

To add column values manually, follow these steps:


1. In the **Workspace** pane, click a reference table.

Columns in the reference table appears.




- 2. Click
- 3. Click

The Add Reference Data page appears.



4. Double-click the cells under the columns and type the respective column values.

Adding Column Values Manually



5. Click .

The column values are added to the reference table.

Importing Column Values from MS Excel Files

You can import reference data from MS Excel files into reference tables. First, you need to add columns to a reference table and then import column values from an MS Excel file. For more information on adding columns to reference tables, refer to the Adding Columns to Reference Tables topic.

To import column values from MS Excel files, follow these steps:


1. In the **Workspace** pane, click a reference table.

Columns in the reference table appear.



- 2. Click
- 3. Click

The Import Table Data page appears.




- 4. Click Choose File and browse and select the XLSX file.
- 5. Click

The Import Table Data page appears.

6. Double-click the **Select Column to Import** cell of the required column.

Column names added by you in the previous steps appear as options.



7. Select the appropriate <Column_Name>.

You can select multiple columns.

8. Click 1.


The column values are imported from the XLSX file.

You can import reference data from a database to a reference table by connecting the database to the application. It involves adding columns to reference table and then importing column values from the database. For more information on adding columns to reference tables, refer to the Adding Columns to Reference Tables topic.

To import column values from databases, follow these steps:


1. In the **Workspace** pane, click a reference table.

Columns in the reference table appear.



- 2. Click .
- 3. Click

The DB Scan page appears.



4. Enter appropriate values in the fields on the Quick Connection tab to establish a connection with a database. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
DB Туре	Specifies the database type.
	For example, Sql Server.
	Specifies the JDBC driver name for connecting to the database.
Driver Name	For example, com.microsoft.sqlserver.jdbc.SQLServerDriver
	The field is autopopulated based on the DB Type.
IP Address/Host	Specifies the IP address or server host name of the database.
Name	For example, localhost.
	Specifies the port to connect with the database.
Port	For example: 1433 is the default port for a Sql Server database
	type.
	Specifies the database name being used to connect to the ref-
Database Name	erence table.
	For example, ErwinDIS931.
User Name	Specifies the user name to connect with the database.


Field Name	Description
	For example, sa.
Password	Specifies the password to connect with the database.
	For example, goerwin@1.

5. Click to test the connection.

If the connection is established, the success message appears.


- 6. Write a query in the **Query Panel** to pull the data from the database.
- 7. Click to validate the query.
- 8. Click to preview the data.

The data is previewed.



9. Double-click the **Select Column to Import** cell under the required column.

A drop-down option appears displaying the reference columns.



10. Choose an appropriate <Reference_Column_Name> from the drop-down.

You can import multiple columns from the database.

11. Click 1.

The column values from the database are imported into the selected reference columns.


Managing Reference Tables

Managing reference tables involves:

- Altering
- Copying
- Assigning users
- Deleting

To manage reference tables, follow these steps:

1. In the **Workspace** pane, right-click a reference table.



2. Use the following options:

Alter Table

Use this option to update a reference table. You can edit table name, owner, data steward, and add or remove columns.

Copy

Managing Reference Tables

Use this option to copy a reference table. You can paste the copied reference table in a reference folder. To paste the reference table, right-click the reference folder and click Paste.

Assign Users

Use this option to assign users to reference tables. Before, you assign a user to a reference table, ensure that the user is assigned to the corresponding reference folder.

On the Assign Users page, select user IDs under User ID list-box and move them to **Assigned Users** list-box using the arrows (or). Similarly, to change existing user assignment, select user IDs under Assigned Users list-box and move them back to **User ID** list-box using the arrows (or ...).

Delete


Use this option to delete a reference table that is no longer required.

Creating Publish Environments

You can publish reference tables to various environments like development, production, test etc. You can also specify the schema of the environment, for example, DBO.


To create publish environments, follow these steps:

- 1. Go to Application Menu > Data Catalog > Reference Data Manager.
- 2. In the **Workspace** pane, right-click the **Environments** node.



3. Click New Environment.

The New Environment page appears.



4. Enter the Environment Name and Schema Name.

For example:

Environment Name: Production

Schema Name: DBO

5. Click

The publish environment is created and saved on the Publish Environments page.


Adding Validation Rules

You can define a validation rule in the form of SQL queries and use it to validate reference tables.

To add validation rules, follow these steps:

- 1. Go to Application Menu > Data Catalog > Reference Data Manager.
- 2. In the **Workspace** pane, click the **Validation Rules** node.

The Validation Rule Grid page appears.



3. Click .

The New Validation Rule page appears.




4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Validation Name	Specifies the name of the validation rule.
	For example, Incorrect_Object_ID.
Validation Descrip- tion	Specifies the description about the validation rule.
	For example: This validation rule validates the ERWIN_SALES ref-
	erence table.
Validation Rule	Specifies the SQL query of the validation rule.
	For example: select * from ERWIN_SALES where ID = 1000000.

5. Click

The validation rule is created and saved in the Validation Rule Grid.



Use the following options to work on the Validation Rule Grid page:

Validation Rule (112)

Use this option to view validation rule queries.



Use this option to update validation rules.

Delete ()

Use this option to delete validation rules that are no longer required.

Once a validation rule is added, you can:

- 1. Associate it with a reference table
- 2. Run validation against the reference table

Associating Validation Rules with Reference Tables


After creating a validation rule, you need to associate the validation rule with a reference table.

This allows you to execute the validation rule to validate data in the reference table.

To associate validation rules with reference tables, follow these steps:

1. In the **Workspace** pane, right-click a reference table.


The available options appear.



2. Click Associate Validations.

The Associate Validation page appears.

Associating Validation Rules with Reference Tables




3. Drag and drop the required validation rule from the Available Validation pane to the Associated Validation pane.

For more information on adding validation rules, refer to the Adding Validation Rules topic.

4. Click

The associated validation rules appear on the Associated Validations tab.




Running Validations Against Reference Tables

You can run a validation rule query against a reference table after associating the table with the validation rule. Executing validation rule validates the data in the reference table.

To run validation rules against reference tables, follow these steps:

1. In the **Workspaces** pane, click a reference table.

The following page appears. Ensure that you are not in edit mode. If you are in edit mode, click to cancel edit.



2. Click 🥙.

The Validate Table page appears.




3. Select an environment and a validation rule.

For more information on creating environments, refer to the Creating Publish Environments topic.

4. Click

Validation is successfully executed.

The error rows returned by executing the validations are highlighted in red color.




Associating Codesets With Reference Tables

You can associate codesets with columns of a reference table. Codesets can be used as configurable pick lists so that data can be selected from the drop-down.

To associate codesets with columns of reference tables, follow these steps:

- 1. Go to Application Menu > Data Catalog > Reference Data Manager.
- 2. In the **Workspace** pane, right-click a reference table.


The available options appear.



Click Associate Codesets.


The Associate Codeset page appears.

Associating Codesets With Reference Tables



4. Double-click the cell for the required column and select an appropriate codeset.


For more information on codesets, refer to the Maintaining Enterprise Codesets section.



5. Click .

The codeset is associated with the column of the reference table.

The corresponding column in the reference table is now configured as a drop-down and populated with values from the selected codeset.




Versioning Reference Tables

You can create versions of reference tables and track the legacy of reference tables. The old version is archived and new version is added to the Reference Table tree in the Workspace pane.


To create versions of the reference tables, follow these steps:

- 1. Go to Application Menu > Data Catalog > Reference Data Manager.
- 2. In the **Workspace** pane, right-click a reference table.



3. Click New Version.

The New Version page appears.




4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Table Name	Specifies the name of the reference table.
	For example, Data_Classifications_Levels.
Version	Specifies the new version of the reference table.
	For example, 1.02.
	Specifies the description about the reference table.
Description	For example: This reference table serves as domain for the data clas-
	sification column.
Version Label	Specifies the version label of the reference table.
	For example, Beta.
Changed Description	Specifies the description of the changes made in the reference table.
	For example: A new column, Object_ID was added in the reference
	table.

5. Click

The new version of the reference table is created and saved under the Reference Table tree.

The previous version of the reference table is archived.




Publishing Reference Tables

You can publish a reference table to a publish environment. Before publishing a reference table, you must ensure that the table has passed all validations successfully.

To publish reference tables, follow these steps:

- 1. Go to Application Menu > Data Catalog > Reference Data Manager.
- 2. In the **Workspace** pane, right-click a reference table.




3. Click Publish.

A warning message appears.

4. Click Yes.

The Publish Table page appears.

Publishing Reference Tables




5. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Table Name	Specifies the name of the reference table.
	For example, Data_Classifications_Levels.
	It is autopopulated and cannot be edited.
	Specifies the current version of the reference table.
Version	For example, 1.00.
	It is autopopulated and cannot be edited.
Version Label	Specifies the version label of the reference table.
	For example, Beta.
	Specifies the description about the changes made in the reference
Change	table.
Description	For example: A new column, Object_ID was added in the reference
	table.
	Specifies the environment to which the reference table would be pub-
D blish E. I.	lished.
Publish Envir- onment	For example, Production.
Official	For more information on creating publish environment, refer to the
	Creating Publish Environments topic.

6. Click

The reference table is published. The published version is archived and a new version of the reference table is created in the Workspace pane.



The published version is also saved in the Published Tables pane.

Publishing Reference Tables



Associating Reference Tables with Mappings

Reference data sets the permissible values for other data fields. To standardize your data, you can associate a reference table with mappings. Ensure that you publish the required reference table before associating it with mappings.


To associate reference tables with Mappings, follow these steps:

- 1. Go to Application Menu > Data Catalog > Mapping Manager.
- 2. In the Workspace Mappings pane, click a map.

The Mapping Specification grid appears.




- 3. Click .
- 4. Right-click the header menu.



Select the **Reference Table** check box.

The Reference Table column appears in the Mapping Specification grid.

6. Drag the reference table from Reference Table Catalog and drop it on the required row under the Reference Table column.




7. Click .

The reference table is associated with the mappings.

Codeset Manager

To access the Codeset Manager, go to Application Menu > Data Catalog > Codeset Manager. The Codeset Manager dashboard appears:



UI Section	Function	
	Use this pane to browse through Codesets Workspace and Code Mappings	
1-Work-	Workspace panes.	
space	Codesets Workspace enables you to create and categorize codesets. Code Map-	
	pings Workspace enables you to create and categorize code mappings.	
2-Right	Use this pane to work on the data based on your selection in the Workspace	
Pane	pane.	
3-Pub-		
lished	Use this pane to browse, view, and export published codesets.	
Codesets		
4-Retired	Use this pane to browse, view, and export retired codesets.	
Codesets	ose this parie to browse, view, and export retired codesets.	

Managing codesets involves the following:

Codeset Manager

- Maintaining enterprise codesets
- Maintaining code mappings

Maintaining Enterprise Codesets

You can create and maintain codesets using the Enterprise section of the Codeset Manager. Under the Enterprise section, you can create codesets, add code name and code value pairs, and version them. You can also publish the codesets to various environments such as development, test, or production and used it create code crosswalks (mappings).

Maintaining enterprise codeset involves:


- **Creating categories**
- Adding codesets
- Versioning codesets
- **Deleting codes and codesets**
- **Publishing codesets**

Creating Categories

Codes are stored in a hierarchical manner Categories > Codesets. You can group codesets into categories based on your organization's projects, departments, or functions. Therefore, before creating codesets, you need to create a category. You can also create sub-categories to group codesets further.

To create categories, follow these steps:

- 1. Go to Application Menu > Data Catalog > Codeset Manager.
- 2. In the **Codesets Workspace** pane, right-click the **Codesets** node.



3. Click New Category.

The New Category page appears.



4. Enter the Category Name and Category Description.

For example:

- Category Name EDW
- Category Description This category contains three codesets, Country Codes, Gender, and Marital Status.

5. Click .

A category is created and saved in the category tree.

Once a category is created, you can:

- Assign users to the category
- Add codesets to the category

You can also manage it using the options available on the right-clicking category. Managing categories involves:

- Updating categories
- Creating sub categories
- Deleting categories
- Creating new codesets
- Exporting codesets
- Deleting codesets
- Exporting category codesets
- Importing codesets
- Assigning users


Managing Categories

Managing categories involves:

- **Updating categories**
- Creating sub categories
- Deleting categories
- Creating new codesets
- **Exporting codesets**
- Deleting codesets
- **Exporting category codesets**
- Importing codesets
- Assigning users

To manage categories, follow these steps:

1. In the **Codesets Workspace** pane, right-click a category.



2. Use the following options:

New Sub Category

Use this option to create a sub-category and group codesets further.

Delete Category

Use this option to delete a category that is no longer required. Deleting a category also deletes codesets in it.

New Codesets

Use this option to create new codesets. For more information on creating new codesets, refer to the Adding Codesets topic.

Export Codesets

Use this option to export codesets to an XLSX file.

Delete Codeset(s)

Use this option to delete one or multiple codesets in a category. On the Delete Codesets page select a codeset(s) and delete them.

Export Category Codesets

Use this option to export the category codesets to an XLSX file.

Import Codesets

Use this option to import codesets from another category. On the Import Codesets page you can browse and upload files.

Assign Users


Use this option to assign users to a category based on your organization's projects, departments, functions, and so on. On the Assign/Unassign Users page, select or remove users and click . For more information on assigning users, refer to Assigning Users topic.

Assigning Users

You can assign users to a category and enable write access to all sub-folders and codesets within the category.

To assign users, follow these steps:

1. In the **Codesets Workspace** pane, right-click a category.



2. Click Assign Users.



3. Use (or) to move users from User ID box to Assigned Users box and use (or (P) to move users from Assigned Users box to User ID box.

4. Click

The users are assigned to the category.



Follow the same procedure to add/remove users to/from the category.


Adding Codesets

After creating a category, you can add codesets to enter codes.

Codesets store codes in a code value grid.

To add new codesets, follow these steps:

- 1. Go to Application Menu > Data Catalog > Codeset Manager.
- 2. In the **Codesets Workspace** pane, right-click a category.



3. Click New Codeset.

The New Codeset page appears.



4. Enter Codeset Name and Codeset Description.

For example:

- Codeset Name: Country Codes
- Codeset Description: This codeset has code names and code values for four countries.
- 5. Click

A new codeset is created and saved under the Codesets tree.

Once a codeset is created you can add codes to the code value grid in the following ways:


- **Entering codes manually**
- Importing codesets from a MS Excel file
- Importing codesets through a DB scan

After creating codesets, you can add codes manually in the code value grid.

To enter codes manually, follow these steps:


- 1. Go to Application Menu > Data Catalog > Codeset Manager.
- 2. In the Codesets Workspace pane, click a required.

The Code Value Grid appears.



- 3. Click .
- 4. Click

The New Code page appears.




5. Enter appropriate values in the fields. Fields marked a with red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description	
Code Name	Specifies the code name.	
	For example, Admin.	
Codo Value	Specifies the code value of the code name.	
Code Value	For example, 1.	
Code Descrip Specifies the description about the code.		
tion	For example: The code value for Admin is 1.	
System/	Specifies the system and environment related with the code.	
Environment	For example, EDW.EDW-DEV.	
Name	Select the System/Environment name.	
Start Date	Specifies the start date of the code validity.	
	For example, 02/24/2020.	
	Enter the start date using 🛅.	
End Date	Specifies the end date of the code validity.	
	For example, 03/22/2021.	

Field Name	Description
	Enter the end date using
illiser Detined	Switch Activate User Defined Fields to ON to use the user defined fields in the Code Value Grid.
II ICAL HATINAN	You can use your own UI labels for user defined fields. For more information on using UI labels for user defined fields, refer to the Configuring Language Settings topic.

6. Click

The codes are entered into the Code Value Grid.



7. Use the following options:

Maximize

To maximise the Code Value Grid view, click

Export to Excel

To download the codeset, click a.

Managing codesets involves:

- Editing Codesets
- Copying Codesets
- Editing Code Value Grid
- Retiring Codesets

Importing Codes using MS Excel Files

You can import codes into Code Value Grid using .xlsx files. The .xlsx file template must be compatible with the Code Value Grid. To ensure the compatibility, download the template and enter the codes and upload it to the Code Value Grid.

To import codes using MS Excel Files, follow these steps:


- 1. In the **Codesets Workspace** pane, click a codeset.
 - The Code Value Grid appears.
- 2. Click to download the template file.

The template in .xlsx format is downloaded.

3. Enter relevant data in the template.




You can use your own UI labels for user defined fields. For more information on using UI labels for user defined fields, refer to the Configuring Language Settings topic.



- 4. Click at to enable the edit mode.
- 5. Click .

The Import Excel page appears.



- 6. Browse the updated .xlsx file using **Choose File**.
- 7. Click 1.

The codes are uploaded into the Code Value Grid.

Once you upload the codes in the Code Value Grid, you can manage the codesets.

Managing codesets involves:

- **Editing Codesets**
- Copying Codesets
- Editing Code Value Grid
- Retiring Codesets


Importing Codes into Code Value Grid using DB Scan

You can import codes into Code Value Grid by scanning a database. Enter connection parameters and establish a connection between the database and erwin DI. Once the connection is established, write an SQL guery to preview the required data. You can select the required columns and import them as codes into the Code Value Grid.

To import codes using DB scan, follow these steps:


1. In the **Codesets Workspace** pane, click the required codeset.

The Code Value Grid page appears.




- 2. Click , to enable edit mode.
- 3. Click .

The Following page appears.



4. Expand the Quick Connection pane.



5. Enter appropriate values in the fields (connecting parameters). Fields marked with a red asterisk are mandatory. Refer to the following table for field description.

Field Name	Description
	Specifies the database type.
DBType	For example, Sql Server.
	Select the database type from which you wish to scan codes.
	Specifies the JDBC driver name for connecting to the database.
Driver Name	For example, com.microsoft.sqlserver.jdbc.SQLServerDriver
Driver Name	It is autopopulated depending on the DB type. You can also
	update the driver name.
IP Address/Host	Specifies the IP address or server host name of the database.
Name	For example, localhost.
	Specifies the port to connect with the database.
Port	For example: 1433 is the default port for a Sql Server database
	type.
	Specifies the database name being used to connect to the code-
Database Name	set.
	For example, ErwinDIS931.
	Specifies the name of the system related with the codeset.
System Name	For example, EDW.
	The name of the system should be same as provided in
	Metadata Manager.
	Specifies the name of the environment related with the codeset.
System Envir-	For example, EDW-DEV.
onment Name	The name of the environment should be same as provided in
	Metadata Manager.
User Name	Specifies the user name to connect with database.
	For example, sa.
Password	Specifies the password to connect with database.
	For example, goerwin@1.
URL	Specifies the full JDBC URL that is used to establish a connection
	with the database.

Importing Codes into Code Value Grid using DB Scan


Field Name	Description
	For example, jdbc:sqlserver://SERVER_ NAME:PORT#;data-
	baseName=DatabaseName
	It is autopopulated based on the other parameters.

6. Click to test the connection.

On a successful connection, Connection Successful pop-up appears.

- 7. Write an SQL query in the Query Panel to fetch the required data from the database.
- 8. Click to validate the query.
- 9. Click at to preview the data.
- 10. Double-click the **Select CSMHeader Template** cell of the required column.

The columns of the Code Value Grid appears as an option list.



11. Select the required Code Value Grid column.



12. Click to import the selected columns into the Code Value Grid.

The selected columns are imported in the Code Value Grid.

Once you import the codes in the Code Value Grid, you can manage codesets.

Managing codesets involves:

- **Editing Codesets**
- Copying Codesets
- Editing Code Value Grid
- Retiring Codesets

Managing Codesets


Managing Codesets involves the following:

- Editing codesets
- Deleting codesets
- · Creating new codeset version
- Publishing codesets
- Copying codesets
- Retiring codesets

You can manage the codesets and update its details.

To manage codesets, follow these steps:

- 1. In the Codesets Workspace pane, expand a category.
- 2. Expand the **Codesets** node, and right-click a codeset.



3. Use the following options:

Edit Codeset

Use this option to update codeset's details.

Delete Codeset

Use this option to delete a codeset.

New Version

Use this option to create a new codeset version. For more information on creating new codeset version, refer to Versioning Codesets topic.

Publish

Use this option to publish the codesets. For more information on publishing codesets, refer to Publishing Codesets topic.

Сору

Use this option to copy the selecte codeset and paste it in different category.

Retire


Use this option to retire a codeset and it is moved to Retired Codesets pane. After you retire a codeset, you cannot retrieve that codeset.

Versioning Codesets

You can version codesets and maintain the legacy of codesets with a record of changed description.

To create new versions of codesets, follow these steps:


- 1. Go to Application Menu > Data Catalog > Codeset Manager.
- 2. In the **Codesets Workspace** pane, right-click a codeset.



3. Click New Version.

The New Codeset Version page appears.

Versioning Codesets



4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field description.

Field Name	Description
Codeset Name	Specifies the name of the codeset whose version is being created.
	For example, Country Codes.
	It is autopopulated with the codeset name and cannot be edited.
Codeset Version	Specifies the new version of the codeset.
Codeset version	For example, 1.03.
Codeset Description	Specifies the description about the codeset.
	For example: This codeset has code names and code values for four countries.
	It is autopopulated with the codeset description and cannot
	be edited.
Codeset Version Label	Specifies the version label of the codeset.
Codeset Version Laber	For example, Beta.
Codeset Changed	Specifies the description about the changes in the codeset.
Description	For example: Code Value for CANADA was changed to CAN.

5. Click

The new version is created and the older version is archived.


Deleting Codes and Codesets

You can logically delete and restore the codes, and also permanently delete the codesets.

To delete codesets, follow these steps:

- 1. Go to Application Menu > Data Catalog > Codeset Manager.
- 2. In the **Codesets Workspace** pane, expand a category.
- 3. Expand a Codesets node and click a codeset.

The Code Value Grid appears



4. Select Delete Indicator check box for relevant Codeset Name from the Codeset Value Grid.

A warning message appears.

5. Click Yes.


The code is logically deleted and can be restored or purged.

To restore or purge logically deleted codes, follow these steps:

1. Click .

The Logically Deleted Codes page appears.

Deleting Codes and Codesets



- 2. Select required rows.
- 3. Click , to delete the selected rows.
- 4. Click , to restore the selected rows.

To permanently delete codesets, follow these steps:

1. Right-click a codeset.



To delete a codeset, ensure the codeset is in edit mode. Click 🔯 to cancel edit mode.

2. Click Delete Codesets.

A warning message appears.

3. Click Yes.


The codeset is deleted.

Publishing Codesets

You can publish your codesets to an environment. To publish the codesets, ensure that you have created and setup an environment.


To create publish environments, follow these steps:

- 1. Go to Application Menu > Data Catalog > Codeset Manager.
- 2. In the **Codesets Workspace** pane, right-click the **Environments** node.



Click New Environment.

The New Environment page appears.



- 4. Enter Environment Name.
- 5. Click

A new publish environment is created and saved in the Publish Environments pane.


To publish codesets, follow these steps:

- 1. Go to Application Menu > Data Catalog > Codeset Manager >.
- 2. In the Codesets Workspace pane, right-click a codeset.



3. Click Publish.

The Publish Codesets page appears.



4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field description.


Field Name	Description
Codeset Name	Specifies the name of the codeset which is being published.
	For example, Country Codes.
	It autopopulates with the codeset name and cannot be
	edited.
Codeset Version	Specifies the new version of the codeset.
	For example, 1.03.
	It autopopulates with the new version and cannot be edited.
Codeset Version Label	Specifies the version label of the codeset.
	For example, Beta.
Codeset Changed	Specifies the description about the changes in the codeset.
Description	For example: Code Value for CANADA was changed to CAN.
Publish Environment	Specifies the publish environment to which the codeset is

Publishing Codesets

Field Name	Description
	being published.
	For example, Production.

5. Click .

The codeset is published successfully and the published codesets move under Published Codesets pane.



Once the source and target codesets are published, you can create code mappings.



You can create code mappings without publishing source or target codesets, but it is recommended that you create code mappings after publishing the codesets.

Maintaining Code Mappings

The Codeset Mappings section in Codeset Manager allows you to define and categorize code mappings. The process is standardized with ability to version and publish code mappings to various environments. Further, these published code mappings can be associated with data item mappings in the Mapping Manager.

Maintaining Code Mapping involves:


- **Creating Categories**
- Creating code maps
- Versioning codemaps
- Publishing and association codemaps

Creating Categories

Code maps are stored in a hierarchical manner Categories > Mappings. You can also create sub-categories under a category to provide one more level of categorization to mappings.

To create a category, follow these steps:

- 1. Go to Application Menu > Data Catalog > Codeset Manager > Codeset Mappings.
- 2. In the **Code Mappings Workspace** pane, right-click the **Code Mappings** node.



3. Click New Category.

The New Category page appears.



4. Enter Category Name and Category Description.


For example:

- Category Name: EDW
- Category Description: This category contains two code mappings, Gender Crosswalk and Marital Status Crosswalk.
- 5. Click

A new category is created and saved under the category tree.


To create sub-categories under a category, follow these steps:

1. Under the **Code Mappings Workspace** pane, right-click the required category.



2. Click New Sub Category.

The New Category page appears.



3. Enter Category Name and Category Description.

For example:

- Category Name: EDW-Finance
- Category Description: This sub-category contains two code mappings, Gender Crosswalk and Marital Status Crosswalk.
- 4. Click

A new sub-category is created and saved under the sub-category tree.

Once a category is created, you can:

- Creating code crosswalks for mappings
- Verisoning code maps
- Associating code maps with data item mappings

You can also manage it using the options available on the right-clicking category. Managing categories involves:

- Updating categories
- Deleting categories
- Importing legacy maps
- Assigning users

Managing Categories

Managing categories involves:

- Updating categories
- Deleting categories
- Importing legacy maps
- Assigning users


To manage categories, follow these steps:

1. In the **Codesets Mappings** pane, click a category.

The Category Mapping Grid appears.



2. Right-click a category.



3. Use the following options:

Edit Category

Use this option to update the category's details.

Delete Category

Use this option to delete a category. Deleting a category also deletes the maps

Import Legacy Maps

Use this option to import old maps to the catalog.

Assign Users

Use this option to assign users to a category based on your organization's projects, departments, functions, and so on.

You can create code crosswalks (mappings) for the source and target codesets in the Codeset Manager. These codesets can have the same or different code values. Using the Auto-Map functionality, you can map source and target codesets with:


- Same code values
- Different code values

Creating Code Crosswalks - Source and Target Codesets with Same Code Value

You can use Auto-Map functionality to map source and target codesets having same code values.


To create code mappings when source and target codesets have same code values, follow these steps:

Right-click the required category.



2. Click New Map.

The New Codeset Map page appears.




3. Enter the Codeset Map Name and Codeset Map Description.

For example:

- Codeset Map Name: Gender Crosswalk
- Codeset Map Description: The codeset map is the code mappings between the two codesets, Misc Gender Codes and Gender.
- 4. Select the Source Codeset/System and Target Codeset/System.
- 5. Select the Auto Map check box and click ...

A new code mapping is created and source and target codesets are mapped in the Codeset Mapping Grid.




6. Click to validate the code mapping.

Creating Code Crosswalks - Source and Target Codesets with Different Code Value

Codesets having different code values can be mapped using the drag and drop method.


To create code mappings when source codesets and target codesets have different code values, follow these steps:

1. Right-click the category.



2. Click New Map.

The New Codeset Map page appears.




3. Enter the Codeset Map Name and Codeset Map Description.


For example:

- Codeset Map Name: Gender Crosswalk
- Codeset Map Description: The codeset map is the code mappings between the two codesets, Misc Gender Codes and Gender.
- 4. Select the Source Codeset/System.
- 5. Click

The source codesets details are updated in the Codeset Mapping Grid.



- 6. Click .
- 7. Scroll to right of the Codeset Mapping Grid to see the Target Code Value column.
- 8. In Codeset Tree, expand the target category and the Codesets node.
- 9. Drag and drop the target codeset into the Code Set Mapping Grid under the Target Code Value column.



10. Click ...

The code mappings are successfully saved.

11. Click * to validate the code mapping.

The code map is validated. Ensure that all the required codes are mapped.

Use the following options:

Export

Extend Mapping Grid

To extend the Codeset Mapping Grid, click

Once the code map is created, you can:

- **Edit Code Mappings**
- Create new version of the code map
- Publish and associate the code map with data item mappings


Editing Code Mappings

You can update source codesets and target codesets in the Codeset Mapping Grid.

To update source codesets, follow these steps:

- 1. Go to Application Menu > Data Catalog > Codeset Manager > Codeset Mappings.
- 2. In the **Code Mappings Workspace** pane, expand a category and click a codemap.

The Codeset Mapping Grid and CSMMapSpec Overview pane appears.



3. In **CSM Mapping Overview** pane, click **2**.


You can update Codeset Map Name and Codeset Map Description.



- 4. Select a new Source Codeset and Source System/Environment.
- 5. Select a Target Codeset and Target System/Environment.
- 6. Click


Editing Code Mappings

The Codeset Mapping Grid is updated with the new source codeset. But, the target codeset doesn't update in the Codeset Mapping Grid. You need to drag and drop target codeset from the Codeset Tree to Codeset Mapping Grid.



To update target codeset in the Codeset Mapping Grid, follow these steps:

1. In the Codeset Mapping Grid, click 🕍 .




- 2. In the Codeset Tree, expand the target category and the **Codesets** node.
- 3. Drag and drop the target codeset into the Code Set Mapping Grid under the Target Code Value column.
- 4. Click

The target codeset is updated in the Codeset Mapping Grid.

To update target code values in the Codeset Mapping Grid, follow these steps:

- 1. In the Codeset Mapping Grid, click .
- 2. Double-click a cell under the Target Code Value column and update it with the one of the options available.



3. Click .

The target code values are updated.


Versioning Code Mappings

You can create versions of code mappings and track legacy of a code map.

The new version is available in the Code Mappings Workspace under the Mappings tree.


To create new versions of code mappings, follow these steps:

- 1. Go to Application Menu > Data Catalog > Codeset Manager > Codeset Mappings.
- 2. In the **Code Mappings Workspace** pane, right-click a codeset map.



- 3. Click New Version.
- 4. The New Codeset Map Version page appears.

Versioning Code Mappings



5. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Codeset Map	Specifies the name of the codeset map.
Name	For example, Gender Crosswalk.
Codeset Map	Specifies the new version of the codeset map.
Version	For example, 1.02.
Codeset Map Description	Specifies the description about the codeset map.
	For example: The codeset map is the code mappings between the
	two codesets, Misc Gender Codes and Gender.
Map Version	Specifies the version label of the codeset map.
Label	For example, Beta.

6. Click

The new version is created and saved in the Mappings tree while the older version is archived.

Associating Code Maps with Data Item Mappings

A code map can be associated with a data item mapping to standardize data across the organization. These code maps are maintained in Codesets Manager. For more information on codesets and code mappings, refer to the Codeset Manager section.


Before associating a code map with data item mappings, ensure that you publish the code map.

Publishing Code Maps

To publish code maps, follow these steps:


- 1. Go to Application Menu > Data Catalog > Codeset Manager > Codeset Mappings.
- 2. In the **Code Mappings Workspace** pane, right-click a code map.

The available options appear.



3. Click Publish.

The Publish Codeset Map page appears.



4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Codeset Map	Specifies the name of the code map.
Name	For example, Gender Crosswalk.
Codeset Map Version	Specifies the new version of the code map.
	For example, 1.02.
Codeset Map Description	Specifies the description about the code map.
	For example: The codeset map is the code mappings between the
	two codesets, Misc Gender Codes and Gender.
Map Version Label	Specifies the version label of the code map.
	For example, Beta.
Map Changed Description	Specifies the description about the changes made in the code map.
	For example: Code values were updated.
Publish Envir- onment	Specifies the environment where the code map is being published.
	For example, test.
	You can create publish environments in Enterprise Codesets.


Associating Code Maps with Data Item Mappings

Field Name	Description
	For more information on creating publish environments, refer to the
	Publishing Codesets topic.

5. Click

The code map is published and it can be found in the Published Code Mappings pane under the selected Publish Environment.

A new version of the code map is created under the Mappings tree.




A published code map can be associated with a mapping in the Mapping Manager. The published code map is available under the Code Mappings Catalog.

Associating Code Maps


To associate published code maps with data item mappings, follow these steps:

- 1. Go to Application Menu > Data Catalog > Mapping Manager.
- 2. In the **Workspace Mappings** pane, click the required map.

The Mapping Specification grid appears.



- 3. Click 2.
- 4. In the Mapping Specification grid, right-click the header menu.



Select the **CSM Mapping** check box.

The CSM Mapping Column appears in the Mapping Specification grid.

- 6. In the right pane, expand Code Mapping Catalog.
- 7. Drag the code map into the Mapping Specification grid and drop it under the CSM Mapping column for the required row.

8. Click .

The code map is associated with the data item mappings.