

erwin Data Modeler

DM Connect for DI

Release 12.5

Legal Notices

This Documentation, which includes embedded help systems and electronically distributed materials (hereinafter referred to as the "Documentation"), is for your informational purposes only and is subject to change or withdrawal by Quest Software, Inc and/or its affiliates at any time. This Documentation is proprietary information of Quest Software, Inc and/or its affiliates and may not be copied, transferred, reproduced, disclosed, modified or duplicated, in whole or in part, without the prior written consent of Quest Software, Inc and/or its affiliates

If you are a licensed user of the software product(s) addressed in the Documentation, you may print or otherwise make available a reasonable number of copies of the Documentation for internal use by you and your employees in connection with that software, provided that all Quest Software, Inc and/or its affiliates copyright notices and legends are affixed to each reproduced copy.

The right to print or otherwise make available copies of the Documentation is limited to the period during which the applicable license for such software remains in full force and effect. Should the license terminate for any reason, it is your responsibility to certify in writing to Quest Software, Inc and/or its affiliates that all copies and partial copies of the Documentation have been returned to Quest Software, Inc and/or its affiliates or destroyed.

TO THE EXTENT PERMITTED BY APPLICABLE LAW, QUEST SOFTWARE, INC. PROVIDES THIS DOCUMENTATION "AS IS" WITHOUT WARRANTY OF ANY KIND, INCLUDING WITHOUT LIMITATION, ANY IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NONINFRINGEMENT. IN NO EVENT WILL QUEST SOFTWARE, INC. BE LIABLE TO YOU OR ANY THIRD PARTY FOR ANY LOSS OR DAMAGE, DIRECT OR INDIRECT, FROM THE USE OF THIS DOCUMENTATION, INCLUDING WITHOUT LIMITATION, LOST PROFITS, LOST INVESTMENT, BUSINESS INTERRUPTION, GOODWILL, OR LOST DATA, EVEN IF QUEST SOFTWARE, INC. IS EXPRESSLY ADVISED IN ADVANCE OF THE POSSIBILITY OF SUCH LOSS OR DAMAGE.

The use of any software product referenced in the Documentation is governed by the applicable license agreement and such license agreement is not modified in any way by the terms of this notice.

The manufacturer of this Documentation is Quest Software, Inc and/or its affiliates.

Provided with "Restricted Rights." Use, duplication or disclosure by the United States Government is subject to the restrictions set forth in FAR Sections 12.212, 52.227-14, and 52.227-19(c)(1) - (2) and DFARS Section 252.227-7014(b)(3), as applicable, or their successors.

Copyright © 2025 Quest Software, Inc and/or its affiliates All rights reserved. All trademarks, trade names, service marks, and logos referenced herein belong to their respective companies.

Contact erwin

Understanding your Support

Review support maintenance programs and offerings.

Registering for Support

Access the erwin support site and register for product support.

Accessing Technical Support

For your convenience, erwin provides easy access to "One Stop" support for all editions of erwin Data Modeler, and includes the following:

- Online and telephone contact information for technical assistance and customer services
- Information about user communities and forums
- Product and documentation downloads
- erwin Support policies and guidelines
- Other helpful resources appropriate for your product

For information about other erwin products, visit http://erwin.com/products.

Provide Feedback

If you have comments or questions, or feedback about erwin product documentation, you can send a message to techpubs@erwin.com.

News and Events

Visit <u>News and Events</u> to get up-to-date news, announcements, and events. View video demos and read up on customer success stories and articles by industry experts.

Contents

| DM Connect for DI Overview | 7 |
|---|----|
| Workflow | 7 |
| Prerequisites | 10 |
| erwin Mart Portal System Requirements | 10 |
| erwin DI System Requirements | 12 |
| Database Server Specifications | 13 |
| Permissions | 13 |
| Minimum erwin Mart Permissions | 13 |
| Minimum erwin DI Permissions | 13 |
| erwin DI DocumentsPath | 15 |
| Configuration | 16 |
| Scenario: Schedule Jobs to Export Data Models to erwin DI | 19 |
| Case I: Run Job | 26 |
| Case II: Modify Job | 26 |
| Case III: Recurring Job-No Change in Models | 26 |
| Case IV: New Model in the Folder | 27 |
| Scenario: Schedule Jobs to Import Data Models from erwin DI to erwin DM | 28 |
| Scenario: Import Source and Target Data into Mapping Manager | 35 |
| Scenario: NSM Files | 37 |
| Case I: One NSM File, Multiple Models | 38 |
| Case II: Multiple NSM Files, Multiple Models | 38 |
| Scenario: View Logs | 30 |

| Reference: Data Sharing between erwin DM and erwin DI | . 40 |
|---|------|
| Limitations | .43 |

DM Connect for DI Overview

erwin now offers an integration, DM Connect for DI, between two powerful products, erwin Data Modeler erwin DM) and erwin Data Intelligence (erwin DI). This offering enables you to maintain a single metadata and glossary source across erwin DM and erwin DI using erwin Mart Portal as an interface. Apart from this, DM Connect for DI offers the following benefits

- Use data models as a foundation for data governance initiatives
- Automatically update data catalog
- Maintain a business glossary based on naming standards


Workflow

erwin DM supports several target databases. It provides a powerful and robust workspace to create rich data models based on these target databases. Further, it provides connectivity to erwin Mart Portal; where you can store your rich data models in a mart repository.

erwin Mart Portal acts an interface between erwin DM and erwin DI. It enables you to schedule jobs to export data models and data sources from your mart repository to erwin DI Data Catalog and vice versa. Further, it integrates the naming standards set up on your models into the Business Glossary Manager.

erwin DI enables you to use your data models as a foundation for your data governance initiatives. It enables you to maintain a semantic lineage between metadata and business objects.

To summarize, erwin Data Modeler, erwin Mart Portal, and erwin DI work together as follows.



The following table explains the erwin DM, erwin Mart Portal, erwin DI version compatibility:

| Products- Versions | erwin DI 10.0 | erwin DI 10.1 | erwin DI 10.2 | erwin DI 11 | erwin DI 11.5 | erwin DI 12.0 | erwin DI 12.1 | erwin DI 13.0 |
|--------------------------------|---------------------|---------------------|---------------------|-------------------|---------------------|---------------------|---------------------|---------------------|
| erwin Mart Portal 2021R1 | Yes | Yes | Yes | Yes | Yes | No | No | No |

DM Connect for DI Overview

| Products- Versions | erwin DI |
|-----------------------------|-------------|-------------|-------------|-------------|-------------|-------------|-------------|-------------|
| | 10.0 | 10.1 | 10.2 | 11 | 11.5 | 12.0 | 12.1 | 13.0 |
| erwin Mart Portal 12.0 | Yes | Yes | Yes | Yes | Yes | No | No | No |
| erwin Mart Portal 12.1 | No | No | No | No | No | Yes | Yes | Yes |
| erwin Mart Portal 12.5 | No | Yes |
| erwin Mart Portal 12.5.1 | No | Yes |
| erwin Mart Portal 12.5.2 | No | Yes |

Prerequisites

Before configuring erwin DM Connect for , ensure that the prerequisites for erwin Mart Portal and erwin Data Intelligent (erwin DI) are in place:

- System requirements:
 - erwin Mart Portal
 - erwin DI
- Permissions:
 - erwin Mart Portal
 - erwin DI
- erwin DI DocumentsPath

erwin Mart Portal System Requirements

Refer to the following tables for minimum system requirements.

| Parameter | Requirement |
|----------------------|---|
| Hardware/Workstation | Windows-based workstation 16 GB RAM 100 GB of disk space or more as required to support your specific mart |
| Operating System | Microsoft Windows Server 2016 Microsoft Windows Server 2019 Microsoft Windows Server 2022 Microsoft .NET Framework 4.0 and above All current Microsoft Windows critical updates |
| | Microsoft SQL Server 2016 SP2 or the certified versions 2017 and 2019, and Microsoft SQL Azure 12, and Amazon RDS SQL Server 2019 |
| Database | For DM Connect for DI, the minimum SQL Server version requirement is SQL Server 2016 SP2 |
| | Oracle 12c R2, 18c, 19c, and 21c |

Prerequisites

| Parameter | Requirement |
|---|---|
| | PostgreSQL 15.3, 14.8, 13.11, 12.15 and 11.20. You can also use PostgreSQL certified version 11.18 for Amazon Aurora. |
| erwin Mart Portal Web Client - Browser | Microsoft Edge v97 or newer Mozilla Firefox v91 or newer Google Chrome v97 or newer Apple Safari 15 or newer |
| Web Server | Apache Server 2.4.57 |
| JDK | 17.0.7 |
| | In the C:\Program Files\erwin\Mart Portal\create_service.cmd, update the RAM size setting to increase the RAM in MBs: |
| MartPortal Services | reg add "HKLM\SYSTEM\CurrentControlSet\Services\erwinMartPortal\Parameters" /v Application /d "\"%JRE_HOME%\bin\java.exe\" -Xms2048m -Xmx10240m -Dlog-ging.config=\"file:C:\Program Files\erwin\Mart Portal\MartApp\config\log4j2-portal.xml\" -jar \"C:\Program Files\erwin\Mart Portal\MartApp\MartPortal.jar\"" That is, (2GB -10GB) |
| ER360 Services | In the C:\Program Files\erwin\Mart Portal\create_service.cmd, update the RAM size setting to increase the RAM in MBs as follows: reg add "HKLM\SYSTEM\Cur- rentControlSet\Services\erwinER360\Parameters" /v Application /d "\"%JRE_ HOME%\bin\java.exe\" -Xms2048m -Xmx10240m -Dlog- ging.config=\"file:C:\Program Files\erwin\Mart Portal\MartApp\config\log4j2- er360.xml\" -jar \"C:\Program Files\erwin\Mart Portal\MartApp\ER360.jar\"" That is (2GB - 10GB) |
| Vault Services | In the C:\Program Files\erwin\Mart Portal\create_service.cmd, update the RAM size setting to increase the RAM in MBs: reg add "HKLM\SYSTEM\CurrentControlSet\Services\erwinVaultService\Parameters" /v Application /d "\"%JRE_HOME%\bin\java.exe\" -Xms2048m -Xmx4096m -Dlog- ging.config=\"file:C:\Program Files\erwin\Mart Portal\MartApp\config\log4j2- vaultservice.xml\" -jar \"C:\Program Files\erwin\Mart Portal\MartAp- p\vaultservice.jar\"" That is, (2GB -4GB) |

erwin DI System Requirements

| Parameter | Requirement |
|---------------------------------|--|
| Hardware/Workstation | VM or Dedicated Physical Server Processor - 64-bit, minimum 4 cores RAM: 16 GB for limited user POCs 32-64 GB for enterprise production deployment Hard Disk Drive - 200-300 GB |
| Operating System | Microsoft Windows - Windows Server 2016 and above Linux v4.19 and above RHEL 8.0 and 8.5 Amazon Linux 2 |
| Database | SQL Server 2016, 2017, 2019 For DM Connect for DI, the minimum SQL Server version requirement is SQL Server 2016 SP2 Oracle 12c, 18c, 19c |
| Browser | Microsoft Edge v86x or newer Google Chrome v86.0 or higher Mozilla Firefox v82.0 or higher |
| Web Servers | Apache Tomcat v9.0.58 |
| Web Server Memory Allocation | Allot at least 50 percent of available memory. For example, if available memory is 16GB, allot at least 8GB. |
| Web Client Workstation | Processor - i3 or higher RAM - 8GB minimum Minimum Free Space - 1-2GB |

In case of enterprise deployment, for the best performance, it is recommended to allot at least 0.5 GB space per user on the application server. For example, if 30 users log on simultaneously, the application server must have at least 15 GB of RAM allocated to it.

The above RAM allocation does not indicate the RAM of the server machine. It indicates the physical RAM allocation to the application server.

Database Server Specifications

The following table lists database server specifications:

| Parameter | Requirement |
|-----------------|-----------------------------|
| Server Type | Dedicated standalone server |
| Processor | 64-bit, minimum 4-8 cores |
| RAM | 32 GB |
| Hard Disk Drive | 250-500 GB |
| Tablespace | 50 GB, minimum |

erwin DI requires a dedicated schema/database (SQL Server or Oracle) with at least 50 GB tablespace allocated to it, which increases exponentially based on usage.

Permissions

To use DM Connect for DI, you need certain permissions on erwin Mart Portal and erwin Data Intelligence (DI).

Minimum erwin Mart Permissions

You can use DM Connect for DI only if your account has been assigned the following profiles:

- Administrator
- Architect

Minimum erwin DI Permissions

| Metadata Manager | |
|------------------|--|
| Create System | |

Prerequisites

Metadata Manager

Systems/System Tabs/View System Details

List Systems

Systems/Add Environment

Systems/List Environments

Systems/System Environments/Import Environment

Systems/System Environments/New Version

Systems/System Tabs/View Environment Details

Systems/Configure Expanded Logical Name

Systems/System Environments/Environment Tabs/Extended Properties/Edit Extended Properties

Systems/System Environments/Scan Metadata

Systems/System Environments/Environment Tabs/EnvironmentDetails

Mapping Manager

Projects/Create Project

Projects/Mappings/Create Mapping

Projects/Project Tabs/Project Details/View Project Details

rojects/Mappings/Mapping Grid/Edit Mapping Specification Grid (Any one permission in child permissions)

Business Glossary Manager

Custom Objects/Catalog/Create

Custom Objects/Catalog/Edit

Custom Objects/Catalog/View

Custom Objects/Catalog/Custom Objects/Create

Custom Objects/Catalog/Custom Objects/Edit

Business Glossary Manager

Custom Objects/Catalog/Custom Objects/View

Custom Objects/Import Catalog

erwin DI DocumentsPath

To be able to export data from erwin Data Modeler (DM) to erwin DI, ensure that you update the iccdocuments.properties file in erwin DI as follows:

- Windows: If you change the default installation location, follow these steps:
 - 1. Open the **iccdocuments.properties** file from the following location: Apache Software Foundation\Tomcat 8.5\webapps\<Application Name>\WEB-INF\configuration\properties\iccdocuments.properties
 - 2. Change the **DocumentsPath** value to the current installation location: <drivename>:/<application name>

For example, consider you changed the installation location from the default location to:

D:\Apache Software Foundation\Tomcat 8.5\webapps\erwinDISuite\WEB-INF\configuration\properties.

Then, change the **DocumentsPath** to:

D:/erwinDISuite

- **Linux**: Ensure that you follow these steps:
 - 1. Open the **iccdocuments.properties** file from the following location: /opt/tomcat/webapps/<<erwinDISuite>>/WEB-INF/configuration/properties/iccdocuments.properties
 - 2. Change the **DocumentsPath** value to: opt/tomcat/<application name>

For example, change the **DocumentsPath** from *C:/MappingManager* to: opt/tomcat/erwinDISuite

Configuration

To import and export data models, data sources, and naming standards using DM Connect for DI, you need to configure your erwin Data Intelligence (erwin DI) application in erwin Mart Portal.


To configure erwin DI, follow these steps:

1. Go to Application Menu > Settings > DI Configurations. The Configurations page appears.



2. Click 🥰

The Add Configuration page appears.



3. Configure your erwin DI connection parameters as follows:

| Field | Description |
|-----------------------|--|
| Configuration Name | Specify a unique name for the configuration. |
| Server Name | Specify the server address, where erwin DI is installed. |
| Application Name | Specify the name of your erwin DI Application. |

Configuration

| Field | Description |
|--------------------|--|
| Port | Specify the port on your server that is used for erwin DI. |
| Enable SSL | Specify whether you want to connect to the server through a secured connection |
| Username | Specify your erwin DI user name. |
| Password | Specify your erwin DI password. |
| Session Timeout | Specify erwin DI's session time out duration in minutes. |

4. Click **Submit**.

Your connection is tested and saved. You can set up multiple erwin DI configurations and use them as required.

Scenario: Schedule Jobs to Export Data Models to erwin DI

An Export to DI job converts a model to erwin DI compatible format and then,

- exports the model to the Metadata Manager
- exports the source and target column data from a dimensional model into the Mapping Manager

Once source and target column data is exported, any updates made to them are not exported when the job runs again.


If the model has an associated NSM file, it exports the file to the Business Glossary Manager

For more information about data sharing between erwin Data Modeler (erwin DM) and erwin Data Intelligence(erwin DI), refer to the Data Sharing topic.

By default the DM Connect for DI app opens in the Calendar view. You can toggle the page view between the List View () or Calendar View () using the respective buttons on the page toolbar.

To schedule jobs, follow these steps:

- 1. In the header pane, click iii and then click **DM Connect for DI**. The DM Connect for DI page opens.
- 2. Click a suitable calendar slot or click ...
- 3. Click Export to DI. The Schedule Job page appears.



4. Set up job parameters as follows:

| Tab | Field | Description |
|---------|---------------|--|
| Catalog | Select Models | Select models from mart catalog to export. |

Scenario: Schedule Jobs to Export Data Models to erwin DI

| Tab | Field | Description |
|-------------|-------------|---|
| | | The Count field displays the number of selected models. |
| Information | Include NSM | Select whether naming standards must be exported. A catalog named by the NSM file is created under Business Glossary Manager > DM NSM Files custom asset. |
| | | Ensure that the DM NSM Files asset is enabled in erwin DI > Business Glossary Manager Settings. |

Scenario: Schedule Jobs to Export Data Models to erwin DI

| Tab | Field | Description |
|----------------|----------------|---|
| DI Information | Connector Name | Select a configuration to use for the export job. |

Scenario: Schedule Jobs to Export Data Models to erwin DI

| Tab | Field | Description |
|-----|------------------|--|
| | System Name | Enter a system name. This corresponds to System in Metadata Manager. |
| | Environment Name | Use the predefined macros to set the environment name. This corresponds to Environment in Metadata manager. |
| | | For system and environment names, following special characters are allowed: • System: - (hyphen), _ (underscore), and space • Environment: @ (at sign), \$ (dollar sign), & (ampersand), / (slash mark), - (hyphen), _ (underscore), and space All other special characters are replaced with _ (underscore). |
| | | Select a suitable export option: |
| | | Add New: |
| | Export Options | If an environment exists, this option adds any new tables or columns to it. |
| | | If an environment does not exist, this option creates an environment and adds tables and columns to it. |
| | | Update Existing + Add New: |
| | | If the existing model objects have changed, this option exports the updates to the existing model objects in erwin DI. |
| | | Also, it exports any new objects in the model to erwin DI. |
| | | Update Existing + Add New + Invalidate: |
| | | Along with the functionality of Update |

Scenario: Schedule Jobs to Export Data Models to erwin DI


| Tab | Field | Description |
|-----------------|--------------------|--|
| | | Existing + Add New option, this option invalidates any deleted tables or columns. |
| | | Delete & Reload: This option deletes all the tables and columns. Then, it exports them again. |
| | Version | Select whether a version of an existing environment must be created. This archives the existing environment. |
| | Job Name | Specify a job name. |
| | Scheduled Job On | Select the date and time at which the job must run. |
| Job Information | Job Interval | Select a suitable frequency at which the job must run. You can set the job to run once or recur daily, weekly, monthly, or yearly. |
| | Notify Me | Select whether a notification is sent to you when the job status changes. This enables the Notification Email and CC List fields. |
| | Notification Email | Specify the email address at which you want to receive the notification. |
| | CC List | Specify a semi-colon-separated list of email addresses that must receive the job notification. |
| | Run Now | Select the check box to run the job immediately. |

5. Click Submit.

The job is added to the calendar for execution with its **Job State** set to Scheduled.

The job runs according to the schedule and exports data model to Metadata Manager and naming standards to Business Glossary Manager.

Scenario: Schedule Jobs to Export Data Models to erwin DI



Database connection parameters such as DBMS Name/DSN, IP Address/Host Name, Port, and Business Entity Type (System Environment Type) are stored in environment details.



Also, the UDPs and validation rules in the model are exported to the Extended Properties tab in Metadata Manager.

Entity 'CUSTOMER CREDIT' Editor **■** | <u>A</u>* | <u>*</u> ■ | • BIUSA·&· P 8" ∞ ↔ 🕜 Logical Only CUSTOME CUSTOMER CREDI erwin, Inc. erwin Sample Diagram eMovies.erwin EMPLOYEE 8 MOVIE Icon Where Used UDP History Notes Extend **II L** Metadata Manage Create Date 12/31/2007 Table Properties Extended Properties Data Steward Data Ware house_SAS (v1.00) Logical.Color red DateDimension (v1.00) ▲ [No Schema] Source and target column data ▶ ⊞ CUST Logical.Data Steward exported to Mapping Manager CUST_CREDIT

Ⅲ EMF III MO RENT REC

Ⅲ MOVIE ₩ MOVIE_COPY

III MOVIE STORE

PAYMENT

■ STORE

Scenario: Schedule Jobs to Export Data Models to erwin DI

Case I: Run Job

Drawing Objects Physical with Vie

<u></u> = 🦠

The Run Job option immediately runs a job. This option works only if the selected job is a recurring job in the scheduled state.

Case II: Modify Job

The Manage Job option lets you modify an existing scheduled job. If you modify a job:

- before its run schedule, the changes take effect when the job runs
- while it is running, the job is cancelled, and changes are saved. They take effect when the job runs next time.
- after it is past its schedule, the job runs according to the new schedule

Case III: Recurring Job-No Change in Models

Recurring jobs run based on the Job Interval you set while scheduling them. If the models selected in the job have not changed between job intervals, the job still runs according to

Job run on the eMovies model

exports UDPs to the Extended

Properties under Metadata

Manager

the schedule. However, no data is exported to erwin DI.

Case IV: New Model in the Folder

If a new model is added to an existing folder on which a recurring job has been scheduled, DM Connect for DI auto-syncs it to the job. The new model in included in the job automatically, when the job runs next.

Scenario: Schedule Jobs to Import Data Models from erwin DI to erwin DM

An Import to DM job imports environments and the underlying tables, columns, and metadata to a mart catalog in the original file format as a model. You can then, connect to your mart via erwin DMand open the saved model. erwin DMautomatically converts this model to an erwin model. You can save this model locally or on mart. When you save this model back to the mart, it is saved with the corresponding timestamp.


For more information about data sharing between erwin Data Modeler (erwin DM) and erwin Data Intelligence (erwin DI), refer to the Data Sharing topic.

By default the DM Connect for DI app opens in the Calendar view. You can toggle the page view between the List View (=) or Calendar View (=) using the respective buttons on the page toolbar.

To schedule import to DM jobs, follow these steps:

- 1. In the header pane, click and then click **DM Connect for DI**. The DM Connect for DI page opens.
- 2. Click a suitable calendar slot or click
- 3. Click Import to DM.

The Schedule Job page appears.



4. Set up job parameters as follows:


| Tab | Field | Description |
|------------------------|--------------------|--|
| DI Inform- ation | Connector Name | Select a configuration to use for the import job. |
| | System Name | Select a system from the list of available systems based on your DI configuration |
| | Environment Name | Select one or more environments from the list of available environments based on the selected system. |
| Catalog Information | Select Models | Select the mart catalog/library to import models to. |
| | Job Name | Specify a job name. |
| | Scheduled Job On | Select the date and time at which the job must run. |
| Job Inform- ation | Job Interval | Select a suitable frequency at which the job must run. You can set the job to run once or recur daily, weekly, monthly, or yearly. |
| | Notify Me | Select whether a notification is sent to you when the job status changes. This enables the Notification Email and CC List fields. |
| | Notification Email | Specify the email address at which you want to receive the notification. |
| | CC List | Specify a semi-colon-separated list of email addresses that must receive the job notification. |
| | Run Now | Select the check box to run the job immediately. |

5. Click **Submit**.

The job is added to the calendar for execution with its **Job State** set to Scheduled.

On successful job completion, the imported model is added to the selected library in the original erwin DI format. To use this model, you must convert it to erwin DM format.


Scenario: Schedule Jobs to Import Data Models from erwin DI to erwin DM




To convert an imported model to erwin DM format, follow these steps:

- 1. Start erwin DM and connect to your mart.
- 2. On the ribbon, click **Mart** > **Open**.


Scenario: Schedule Jobs to Import Data Models from erwin DI to erwin DM



3. Select the required model and click **Open**. The process to convert the imported model to the erwin DM format runs.




Once this process is complete, the model is converted to .erwin format and opened in the diagram editor.




This model is saved to your mart catalog in the .erwin format with a time stamp. The following image shows the saved model in the Catalog Manager and in your mart library.

Scenario: Schedule Jobs to Import Data Models from erwin DI to erwin DM




Scenario: Import Source and Target Data into Mapping Manager

In case of dimensional model that has associated data sources, DM Connect for DI exports the source and target column data from the model into the Mapping Manager.



Schedule a job on your dimensional model. Once the job is completed successfully, DM Connect for DI creates a project. Under this project, it creates a mapping specification with the source and target column data from your model.


Scenario: Import Source and Target Data into Mapping Manager



Scenario: NSM Files


If the models selected in a job have NSM files associated with them, DM connect for DI exports them to the Business Glossary Manager under the custom asset, erwin DM NSM.

Ensure that the erwin DM NSM asset is enabled under **erwin DI** > **Business Glossary Manager Settings**.



Under the erwin DM NSM asset, each unique NSM file is added as a catalog.

Scenario: NSM Files



Case I: One NSM File, Multiple Models

In a job, if a single NSM file is associated with multiple models, a single catalog is created for both models. The contents of the corresponding catalog under the erwin DM NSM asset type in Business Glossary Manager are overwritten.


Case II: Multiple NSM Files, Multiple Models

In a job, if multiple NSM files are associated with multiple models, multiple catalogs, corresponding to the NSM files are created under the erwin DM NSM asset type in Business Glossary Manager.

Scenario: View Logs

After a job runs, you can view its log to understand more about the job status. In case of failures, you can then troubleshoot using the logs.

To view a job's log, select a job and click View Log.



Reference: Data Sharing between erwin DM and erwin DI

For data to be shared between erwin Data Modeler (DM) and erwin Data Intelligence (DI), the attributes and properties of objects in both the applications must correspond to each other. Refer to the following tables to understand how erwin DM Connect for DI maps data between applications.

| LIBRARY-SYSTEM | |
|----------------------|------------------|
| erwin Data Modeler | erwin DI |
| Library/Catalog Name | System Name |
| Description | Business Purpose |

| MODEL-ENVIRONMENT | | |
|--------------------|--------------------------|--|
| erwin Data Modeler | erwin DI | |
| Model Name | System Environment Name | |
| Model Type | System Environment Type | |
| Version | Version | |
| Description | Intended Use Description | |

| TABLE-TABLE | | |
|--------------------|--------------------|--|
| erwin Data Modeler | erwin DI | |
| Model Name | Environment Name | |
| Library Name | System Name | |
| Entity Name | Logical Table Name | |
| Comment | Table Comments | |
| Schema_Name | Schema | |

COLUMN-COLUMN

Reference: Data Sharing between erwin DM and erwin DI

| erwin Data Modeler | erwin DI |
|--------------------|-------------------------------------|
| Domain Parent | Data Domain |
| Physical Data Type | Data Type, Precision, Length, Scale |
| Null Option | Nullable Flag |
| Foreign Key | Foreign Key Flag |
| Primary Key | Primary Key Flag |
| Child Column Name | Foreign Key Column Name |
| Child Table Name | Foreign Key Table Name |

| UDP-EXTENDED PROPERTIES | | |
|-------------------------|-------------|--|
| erwin Data Modeler | erwin DI | |
| UDP Name | Key Name | |
| Value | Value | |
| Description | Description | |

| NSM-erwin DM NSM | | |
|--------------------|--------------|--|
| erwin Data Modeler | erwin DI | |
| NSM File Name | Catalog Name | |
| Abbreviation | Asset Name | |
| Glossary Word | Definition | |

NSM files have multiple parameters. However, DM Connect for DI is configured to push only the Glossary Word and Abbreviation to erwin DI.

| DATA MOVEMENT SOURCE-MAPPING | |
|------------------------------|---------------|
| erwin Data Modeler | erwin DI |
| Data Source DBMS Type | Database Type |
| DS Transformations | Business Rule |

Reference: Data Sharing between erwin DM and erwin DI

| Library | Target System |
|--|---|
| Model | Target Environment |
| Table | Target Table |
| Column | Target Column |
| Datatype and Length | Target Column Datatype and length |
| Source Library (Or Data Source Name) | Source System |
| Source Model (Or Data Source Server) | Source Environment |
| Source Table (Or Data Movement Table) | Source Table |
| Source Column (Or Data Movement Column) | Source Column |
| Source Column Datatype (Or Data Movement Column Data- type) | Source Column Datatype and length |
| | Check whether datatype and length are added to the corresponding fields. If not, you need to correct it manually. |

Limitations

The following list summarizes the limitations of erwin DM Connect for DI.

- If table's or column's Definition property is updated in a model, the update is not exported when the job is run again. To export the updated Definition, set the job's Export Options to Delete & Reload.
- When you apply an NSM file to a model, it is applied at the model-level. Therefore, it is applied to all versions of the model.
- When you use the validation rules, enure that the names of valid values do not exceed 200 characters, or the validation rules are not exported to DI.