



erwin Data Intelligence

Mapping Management Guide

Release v12.1

Legal Notices

This Documentation, which includes embedded help systems and electronically distributed materials (hereinafter referred to as the Documentation), is for your informational purposes only and is subject to change or withdrawal by Quest Software, Inc and/or its affiliates at any time. This Documentation is proprietary information of Quest Software, Inc and/or its affiliates and may not be copied, transferred, reproduced, disclosed, modified or duplicated, in whole or in part, without the prior written consent of Quest Software, Inc and/or its affiliates

If you are a licensed user of the software product(s) addressed in the Documentation, you may print or otherwise make available a reasonable number of copies of the Documentation for internal use by you and your employees in connection with that software, provided that all Quest Software, Inc and/or its affiliates copyright notices and legends are affixed to each reproduced copy.

The right to print or otherwise make available copies of the Documentation is limited to the period during which the applicable license for such software remains in full force and effect. Should the license terminate for any reason, it is your responsibility to certify in writing to Quest Software, Inc and/or its affiliates that all copies and partial copies of the Documentation have been returned to Quest Software, Inc and/or its affiliates or destroyed.

TO THE EXTENT PERMITTED BY APPLICABLE LAW, QUEST SOFTWARE, INC. PROVIDES THIS DOCUMENTATION AS IS WITHOUT WARRANTY OF ANY KIND, INCLUDING WITHOUT LIMITATION, ANY IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NONINFRINGEMENT. IN NO EVENT WILL QUEST SOFTWARE, INC. BE LIABLE TO YOU OR ANY THIRD PARTY FOR ANY LOSS OR DAMAGE, DIRECT OR INDIRECT, FROM THE USE OF THIS DOCUMENTATION, INCLUDING WITHOUT LIMITATION, LOST PROFITS, LOST INVESTMENT, BUSINESS INTERRUPTION, GOODWILL, OR LOST DATA, EVEN IF QUEST SOFTWARE, INC. IS EXPRESSLY ADVISED IN ADVANCE OF THE POSSIBILITY OF SUCH LOSS OR DAMAGE.

The use of any software product referenced in the Documentation is governed by the applicable license agreement and such license agreement is not modified in any way by the terms of this notice.

The manufacturer of this Documentation is Quest Software, Inc and/or its affiliates Provided with Restricted Rights. Use, duplication or disclosure by the United States Government is subject to the restrictions set forth in FAR Sections 12.212, 52.227-14, and 52.227-19(c)(1) - (2) and DFARS Section 252.227-7014(b)(3), as applicable, or their successors.

Copyright © 2022 Quest Software, Inc. and/or its affiliates All rights reserved. All trademarks, trade names, service marks, and logos referenced herein belong to their respective companies.

Contact erwin

Understanding your Support

Review [support maintenance programs and offerings](#).

Registering for Support

Access the [erwin support](#) site and click Sign in to register for product support.

Accessing Technical Support

For your convenience, erwin provides easy access to "One Stop" support for [erwin Data Intelligence \(erwin DI\)](#), and includes the following:

- Online and telephone contact information for technical assistance and customer services
- Information about user communities and forums
- Product and documentation downloads
- erwin Support policies and guidelines
- Other helpful resources appropriate for your product

For information about other erwin products, visit <http://erwin.com/>.

Provide Feedback

If you have comments or questions, or feedback about erwin product documentation, you can send a message to distechpubs@erwin.com.

erwin Data Modeler News and Events

Visit www.erwin.com to get up-to-date news, announcements, and events. View video demos and read up on customer success stories and articles by industry experts.

Contents

Managing Mappings	12
Using Mapping Manager	13
Creating and Managing Mapping Specifications	15
Creating Projects	16
Adding Documents	19
Assigning Users	22
Assigning Roles	24
Configuring Extended Properties	27
Default Connector	31
Reference Data Manager	36
Importing from Excel	40
Adding Tasks	42
Configuring Task Types	47
Managing Tasks	49
Creating Subject Areas	52
Subject Areas	52
Nested Subject Areas	53
Managing Subject Areas	56
Managing Projects	58
Defining Transformations	60
Configuring Transformation Library	63
Uploading Transformations	66

Downloading Templates	67
Managing Transformations	68
Creating Maps	72
Drag and Drop	78
Creating Mapping Specifications using Metadata Search View	78
Creating Mapping Specifications Using Metadata Tree View	82
Setting Target Update Strategy	84
Graphical Designer	87
Creating Mapping Specifications using Metadata Search View	87
Creating Mapping Specifications using Metadata Tree View	95
Setting Target Update Strategy	101
Auto-Map	104
Creating Mapping Specifications	104
One to Many and Many to Many Mapping Specifications	113
Creating Mapping Specifications Using Metadata Search View	113
Creating Mapping Specifications Using Metadata Tree View	120
Setting Target Update Strategy	123
Adding Transformation and Lookup Details	125
Adding Transformation Details	125
Adding Lookup Details	130
Graphical Designer	132
Adding Transformation Details	132
Adding Lookup Details	136

Updating Mapping Specifications Manually	138
Uploading Mapping Specifications in XML	141
Specifying XPath in Mapping Specifications	144
Setting Column Order and Visibility	146
Column Order	146
Column Visibility	146
Updating Additional Mapping Information	148
Updating Map Spec Overview	151
Updating Source Extract SQL	154
Setting Target Update Strategy	156
Updating Testing Notes	158
Adding Mapping Specification Documents	160
Assigning Mapping Specifications to Users	162
Linking Additional Specification Artifacts	165
Recording Level of Effort	167
Viewing Change Logs	169
Viewing Release Information	170
Adding Tasks	171
Configuring Task Types	175
Managing Tasks	177
Configuring Extended Properties	180
Default Connector	184
Reference Data Manager	189

Importing from Excel	193
Branching and Merging Maps	195
Branching Maps	196
Merging Changes into Parent Maps	199
Deleting Maps	202
Viewing Workflow Logs	204
Analyzing Mappings	206
Generating Virtual Preview of Targets	207
Previewing Data	209
Performing Table Gap Analysis	213
Performing Column Gap Analysis	217
Running Impact Analysis	221
Running Lineage Analysis	222
System	223
Viewing Lineage	223
Working on Lineage	229
Environment	237
Viewing Lineage	237
Working on Lineage	242
Table	248
Viewing Lineage	248
Working on Lineage	255
Column	263

Viewing Lineage	263
Working on Lineage	270
Running End to End Lineage	278
Opening Business View	282
Viewing Mapping Statistics	287
Associating Mappings	289
Associating Code Maps with Data Item Mappings	290
Publishing Code Maps	290
Associating Code Maps	292
Associating Reference Tables with Mappings	295
Linking Requirements to Mappings	297
Publishing and Creating Versions of Mappings	299
Creating Versions of Maps	300
Base-lining Projects	303
Comparing Two Different Mapping Versions	305
Publishing Mappings	307
Publishing Mappings	307
Updating Publishing Details	310
Restoring Archived Maps As Active	312
Exporting Mapping Specifications	315
Proprietary XML Format	316
ETL Jobs	319
Creating and Managing Test Cases for Mappings	322

Creating Test Cases	323
Creating Project-Level Test Cases	323
Creating Map-Level Test Cases	325
Adding Validation Steps	328
Adding Validation Steps to Project-Level Test Cases	328
Adding Validation Steps to Map-Level Test Cases	330
Adding Documents	333
Adding Documents to Project-Level Test Cases	333
Adding Documents to Map-Level Test Cases	335
Managing Test Cases	339
Managing Project-Level Test Cases	339
Managing Map-Level Test Cases	340
Viewing Mapping Manager Dashboard	342
Statistics	344
Mapping Summary	344
Mapping Status	346
Proactive Impact Analysis - Truncation Impacts	348
Project Overview	350
Mapping Classification	351
Mapping Assignments	353
Sources/Targets Not Mapped	354
Test Case Status	356
Project Test Cases	358

User Test Cases	359
-----------------------	-----

Managing Mappings

This section walks you through managing source to target mappings in the Mapping Manager.

Mapping Manager is the core of erwin Data Intelligence (erwin DI), where you do the following:


- Source to target mappings using the Metadata Tree View
- Associate crosswalks to mappings using the Code Mapping Catalog
- Associate reference data to mappings using the Reference Table Catalog
- Associate requirements to mappings using the Specification Artifact Catalog
- Create new mapping versions
- Specify test cases

Once mappings are approved for coding, ETL developers can export them as coding requirements. They can also export the mappings to XML and automatically generate ETL/ELT jobs for ETL tools, such as Informatica PowerCenter, IBM DataStage, Microsoft SQL Server SSIS, and so on.

For further information on accessing and using the Mapping Manager, refer to the [Using Mapping Manager](#) topic.

Using Mapping Manager

To access the Mapping Manager, go to **Application Menu > Data Catalog > Mapping Manager**. The Mapping Manager dashboard appears:



UI Section	Function
1-Workspace Mappings	Use this pane to browse and work on projects and mappings.
2-Central Pane	Based on your selection in the browser pane, use this pane to view or work on the data.
3-Mapping Manager Dashboard	Use this pane to view statistics related to mappings and projects.
4-Published Mappings	Use this pane to view and export details of published mappings.

Managing mappings involves the following:

- [Creating and managing mapping specifications](#)
- [Analyzing mappings](#)
- [Associating mappings](#)
- [Publishing and creating mapping versions](#)
- [Exporting mapping specifications](#)

Using Mapping Manager

- [Creating and managing test cases for mappings](#)
- [Viewing mapping manager dashboard](#)

Creating and Managing Mapping Specifications

After defining systems and uploading metadata in the Metadata Manager, you can create mapping specifications. The Mapping Manager offers multiple ways to create mapping specifications. This section walks you through building metadata driven source to target mapping specifications and enterprise standards to manage them.

Creating and managing mapping specifications involves:


- [Creating projects](#)
- [Defining transformations](#)
- [Creating maps](#)
- [Adding transformations and lookup details](#)
- [Updating mapping specifications manually](#)
- [Uploading mapping specifications in XML format](#)
- [Specifying XPath in mapping specifications](#)
- [Setting column order and column visibility](#)
- [Updating additional mapping information](#)
- [Branching and merging maps](#)
- [Deleting maps](#)
- [Viewing workflow logs](#)

Creating Projects

Projects store and group maps in a hierarchy, Projects > Mappings. You can create an ETL tool-specific project and specify its details, such as project description, project manager, business sponsor, cost center, and IT sponsor.

To create projects, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, right-click the **Projects** node.



3. Click **Create Project**.

The Create Project page appears.

Creating Projects

4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Project Name	Specifies the name of the project. For example, Data Lake Migration. For more information on naming conventions, refer to the Best Practices section.
Description	Specifies the description of the project. For example: The project contains the mapping specifications for the sales data migration.
Project Manager Name	Specifies the project manager's name. For example, John Doe.
Business Sponsor Name	Specifies the business sponsor of the project. For example, ABC Consulting Services.
Project ETL	Specifies the ETL tool assigned to the project. For example, Informatica Pseudocode.
Cost Center	Specifies the cost center of the project. For example, Finance and Accounting.
IT Sponsor Name	Specifies the IT sponsor of the project. For example, XYZ IT Services.

Creating Projects

Field Name	Description
Enable display of Transformation without pseudocode	Specifies whether the transformation is displayed without pseudocode. Switch Enable display of Transformation without pseudocode on (<input checked="" type="radio"/>) to display transformation without pseudocode.

5. Click **Save and Exit**.

A new project is created and added to the project tree.

Once a project is created, you can enrich it further by:

- [Adding supporting project documents](#)
- [Assigning users to the project](#)
- [Configuring extended properties](#)
- [Creating Tasks](#)
- [Creating subject areas](#)
- [Creating maps](#)
- [Tagging projects](#)

You can also manage a project by using the options available on right-clicking the project.

Managing projects involves:

- Uploading legacy maps
- Export mappings
- Export change logs
- Viewing reports
- Sharing links
- Deleting projects
- Viewing workflows


Adding Documents

You can add supporting documents, such as text files, audio files, video files, document links, and so on to a project.

To add documents to projects, follow these steps:

1. In the **Workspace Mappings** pane, click a project.
2. Click the **Project Documents** tab.

The following page appears.



3. Click .


The Add Project Document page appears.

The screenshot shows the 'Add Project Document' form. It includes the following fields and controls:

- Document Name* (text input)
- Document Reference (text input)
- Reference Number (text input)
- Document Link (text input)
- Description (rich text editor with formatting tools)
- Document Owner (text input)
- Document Object (text input)
- Approval Required Flag (checkbox)
- Drag-n-Drop files here or click to select files for upload. (with an upload icon)

Adding Documents


4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.





Option	Description
Document Name	Specifies the name of the physical document being attached to the project. For example, Project Details.
Document Reference	Specifies the name of the reference document. For example, Wikipedia pages.
Reference Number	Specifies the reference number of the reference document. For example, KB_230145.
Document Owner	Specifies the document owner's name. For example, John Doe.
Document Object	Drag and drop or use  to browse and select the document.
Document Link	Specifies the URL of the document. For example, https://drive.google.com/file/d/2sC2_SZlYeFKI70On-b5YkMBq4ptA7jhg5/view
Description	Specifies the description of the document. For example: The document is to keep a record of description and data dictionary of the system.
Approval Required Flag	Specifies whether the document requires approval or not. Select the Approval Required Flag check box to select the document status.
Document Status	Specifies the status of the document. For example, In Progress. Select the status of the document from the drop down. This field is available only when the Approval Required Flag check box is selected.

5. Click .

The project document is saved in the Project Documents Grid.

Adding Documents



Document Type	Document Link	Document Status	Document Owner	Description	Options
pdf	https://erwin.com/	InProgress	Samuel		   

Once a supporting document is added, use the following options:

Information (i)

Use this option to view the document information.

Download (↓)

Use this option to download the document.

Edit (✎)

Use this option to update the document details.

Delete (✕)

Use this option to delete the document that is not required.


Assigning Users

You can assign one or more members of your team to a project. Team members assigned to a project have write access to all mappings under it. Ensure that the roles assigned to the users have the required permissions.

To assign users, follow these steps:


1. In the **Workspace Mappings** pane, click a project.
2. Click the **Project Users** tab.



The Project Users page appears.





3. Click .

The Assign Project Users page appears.



4. Select user IDs under User ID list-box and move them to Assigned Users list-box using the arrows ( or ). Similarly, to change existing user assignment, select user IDs

Assigning Users













under Assigned Users list-box and move them back to User ID list-box using the arrows ( or ).



You cannot assign users with Administrator role to projects.

5. Click .

The selected users are assigned to the project.

Project Users						
#	User ID	User Full Name	Assigned Role	Email ID	Manager Name	View Edit Delete
1	esimpson	Erica Simpson	Data Owner_GER	e.simpson@xyz.		  
2	jadams	Joey Adams	Tech Data Steward_GER	jadams@xyz.cor		  
3	janedoe	Jane Doe	Mapping Designer	jane.doe@edufir	K.Sridhar	  
4	jwilson	Joey Wilson	Tech Data Steward_RO	jwilson@xyz.cor		  

Use the following options to work on the project users list:

Information ()

Use this option to view project user details, such as telephone number, company, and the assigned responsibility.

Edit ()

Use this option to update project user details, such as assigned role and assigned responsibility.

Delete ()

Use this option to remove a user from the project users list.


Assigning Roles

You can assign one or more roles to a project. Users assigned to these roles get write access to all the mappings in the project. Ensure that the roles have the required permissions to access the Mapping Manager.

To assign roles, follow these steps:

1. In the **Workspace Mappings** pane, click a project.
2. Click the **Project Roles** tab.

The Project Roles page appears.



#	Role Name	Role Description	Role Users
1	Data Owner_RO	This role is accountable for who has access to information assets within their functional areas ft	View
2	Data Steward_RO	This role is responsible for utilizing Romania's data governance processes to ensure fitness	View
3	Mapping Admin	Administers Mapping Manager module to define, edit or delete any mapping in any project irres	View

3. Click .

The Assign/Unassign Roles page appears.

Assigning Roles

Assign/Unassign Roles				
#	Select Role	Role Name	Role Description	Role Users
	<input type="checkbox"/>	<input type="text"/>	<input type="text"/>	
1	<input checked="" type="checkbox"/>	Data Owner_RO	This role is accountable for who has access to information assets within their functional areas for Romania. It may decide to review and authorize each access request individually or may define a set of rules that determine who is eligible for access based on business function, support role, etc.	View
2	<input checked="" type="checkbox"/>	Data Steward_RO	This role is responsible for utilizing Romania's data governance processes to ensure fitness of data elements - both the content and metadata.	View
3	<input checked="" type="checkbox"/>	Mapping Admin	Administers Mapping Manager module to define, edit or delete any mapping in any project irrespective to project assignment	View
4	<input type="checkbox"/>	Mapping_Tester		View
5	<input type="checkbox"/>	Tech Data Steward_UK	This role is responsible to answer how data is created, transformed, stored, and moved in technical systems for UK.	View

4. Select the required roles.

5. Click .

The selected roles are assigned to the project.

Project Roles			
#	Role Name	Role Description	Role Users
1	Data Owner_RO	This role is accountable for who has access to information assets within their functional areas fr	View
2	Data Steward_RO	This role is responsible for utilizing Romania's data governance processes to ensure fitness	View
3	Mapping Admin	Administers Mapping Manager module to define, edit or delete any mapping in any project irres	View
4	Tech Data Steward_UK	This role is responsible to answer how data is created, transformed, stored, and moved in technr	View

You can view the users assigned to roles. To view Role Users, click **View**.

For example, the following Role Users page displays the users assigned to the Data Owner_RO role.

Assigning Roles


Role Users	
User ID	User Full Name
1 ksridhar	Kartik Sridhar
2 srahim	Syed Rahim

Configuring Extended Properties


You can configure user-defined project properties under the Extended Properties tab. First, you need to set up a form and then use it to configure the user-defined extended properties.

To configure extended properties of projects, follow these steps:

1. In the **Workspace Mappings** pane, click a project.
2. Click the **Extended Properties** tab.




3. Click **Configure**.



Configuring Extended Properties

The **Extended Properties Configuration** page contains the following sections:

- **Field Controls:** Use this pane to get the required UI elements.
 - **Configure Form:** Use this pane to design forms using the UI elements available in the **Field Controls** pane.
 - **Properties:** Use this pane to view the properties of the UI element selected in the **Configure Form** pane.
4. Click **Edit**. Then, double-click or drag and drop the required UI elements from the **Field Controls** pane to the **Configure Form** pane.
 5. Select UI elements, one at a time, and configure their properties in the **Properties** pane.



Property	Value
Published	ON
Field	Rich Editor
Type	Rich Editor
Dependencies	Type or click here
Configure Values	Configure
Mandatory	OFF
Regular Expression	

Note: 1. Double click on the field cell to update the field name.
2. Select the field name to update its properties



The available properties differ based on the type of UI element.

Refer to the following table for property descriptions:

Property	Description
Published	Switch Published to ON to publish the field.
Field	Specifies the field label.

Configuring Extended Properties

Property	Description
	To change the field labels, double-click the corresponding Value cell. For example, Project Approved On.
Type	Specifies the type of the field. To select field types, double-click the corresponding Value cell. For example, Date Picker.
Dependencies	Defines the pick list that can be used as controlling fields. It works only with the Reference Data Manager connector. To define pick list, select the fields from the drop down option.
Configure Values	Specifies the connectors for the field. To enter option values, click Configure Values . Use the following options: <ul style="list-style-type: none"> ▪ Default connector: Use this option to enter option values manually or using an MS Excel file. ▪ Reference Data Manager: Use this option to pull option values from reference tables in the Reference Data Manager.
Mandatory	Specifies whether the field is mandatory.
Description	Specifies the field description. To enter field descriptions, double-click the corresponding Value cell.
Visible in Extended Properties	Switch Visible in Extended Properties to ON to make it visible on the Extended Properties tab.
Order	Specifies the order of the field on the Extended Properties tab. To enter the order number, double-click the corresponding Value cell. You can also drag and move fields in the Configure Form pane to change their order.

6. Click **Save**.

The form is saved, and is available on the **Extended Properties** tab.

Configuring Extended Properties

You can download extended properties in the XLSX format and use it as a template to [import extended properties](#). To download extended properties, on the **Extended Properties** tab, click **Export To Excel**.

Default Connector

When you configure extended properties using UI elements, such as combo box, radio button, and list, you also need to configure their option values. You can use the default connector to import option values from an MS Excel file or enter them manually.


To configure option values using the default connector, follow these steps:

1. In the **Configure Form** section, click the required UI element.

Ensure that you are in edit mode.

2. In the **Properties** section, click **Configure**.


The Connectors page appears.



3. On the **Connectors** page, ensure that the Default Connector option is selected. Then, click **Next**.

The <UI_Element> Options page appears. For example, if the UI element is Combo Box, the Combo Box Options page appears.

Default Connector



The screenshot shows a window titled "Combo Box Options" with a dark header bar containing window control icons. Below the header are four buttons: "Add" (blue), "Save" (orange), "Delete" (red), and "Import Excel" (green). The main content area is divided into two columns: "Text" and "Value", each with an empty text input field.

4. Use the following options:

Add

Use this option to enter text and value manually.

Import Excel

Use this option to import options from MS Excel files.

5. After configuring option values, click **Save**.

To add option values manually, follow these steps:

1. Click **Add**.
2. Enter values to the Text and Value fields.

The Text corresponds to options whereas the Value corresponds to underlying value of an option. You can add as many values as needed.

Default Connector

Text	Value
<input type="text"/>	<input type="text"/>
Data Steward_GER	rcooper
Data Steward_ROM	vsmith
<input type="text"/>	

3. Click **Save**.

The option values appear in the UI element under the Configure Form section.

Combo Box


- Select an option
- Select an option
- Data Steward_GER
- Data Steward_ROM

To import option values from MS Excel files, follow these steps:

1. Click **Import Excel**.

The Upload Excel page appears.

Default Connector



2. Click **Choose File** and select the required MS Excel file.

The Upload Excel page appears. It displays the data in the MS Excel file.

#	GROUP NAME	ROLE NAME	USER ID
#	Select Column To Import	Select Column To Import	Select Column To Import
1	Data Stewards	Data Steward_GER	mmannigan
2	Data Stewards	Data Steward_GER	mmenza
3	Data Stewards	Data Steward_GER	mmannigan

3. Double-click the **Select Column To Import** cell in the required column.

The available options appear.

#	GROUP NAME	ROLE NAME	USER ID
#	Select Column To Import	Select Column To Import	Select Column To Import
1	Data Stewards	Data Steward_GER	mmannigan


Default Connector

4. Select the appropriate option.

Field corresponds to options and Value corresponds to value of an option. You can import multiple columns. Use Clear Selection to undo the selection.

5. Click .


The <UI_Element> Options page appears. It displays the imported columns. You can delete a row that is not required. To delete rows, click a row and then click **Delete**.




Text	Value
Data Steward_GER	mmanigan
Data Steward_UK	rcooper
Data Owner_GER	esimpson
Data Owner_RO	ksridhar
Tech Data Steward_GER	jadams

6. Click **Save**.

The option values appear in the UI element under the Configure Form section.



Combo Box Select an option 

List

- Select an option
- Data Steward_GER
- Data Steward_UK
- Data Owner_GER
- Data Owner_RO
- Tech Data Steward_GER
- Mapping Admin
- ETL Developer
- Mapping Designer

Reference Data Manager

When you configure extended properties using UI elements, such as combo box, radio button, and list, you also need to configure their option values. You can use the Reference Data Manager connector to import option values from tables in the Reference Data Manager.


To configure option values using reference data manager connector, follow these steps:

1. In the **Configure Form** section, click the required UI element.

Ensure that you are in edit mode.


2. In the **Properties** section, click **Configure**.

The Connectors page appears.




3. On the **Connectors** page, click **Reference Data Manager** and then click **Next**.

The Reference Data Manager page appears. It displays the reference folders in the Connector View pane.



4. In the **Connector View** pane, expand a reference folder and select a reference table. The Parameters pane displays the columns in the reference table. You can also click Preview to view the data in the reference table.

Reference Data Manager



5. In the **Parameters** pane, click the radio button next to the required column.
You can select the controlling field from the drop down option. Ensure that you define the required dependencies in the Properties pane and that the option values for controlling field are configured using the same reference column.
6. Click **Finish**.
The Extended Properties Configuration page appears.

Reference Data Manager

The screenshot shows the 'Extended Properties Configuration' window. At the top, there are 'Save', 'Cancel', and 'Delete' buttons. Below is the 'Field Controls' section with icons for Group, Text Box, Combo Box, List, Radio, Check Box, Number, Boolean, Date Picker, and Category. The 'Configure Form' section contains a 'Selected Roles Group' dropdown with 'Compliance Officer' selected, and a 'List of Cities' dropdown with 'Los Angeles' selected. A 'Radio' control is visible at the bottom. The 'Properties' section on the right has a table with 'Property' and 'Value' columns. The 'Load On Startup' property is set to 'OFF' and 'Visible in Extended Properties' is set to 'ON'.

7. Under the **Properties** section, switch **Load on Startup** to **ON**.
8. Click **Save**.

The option values are configured. For example, in the following form the List of Cities is the controlling field for Selected City. Both the fields get their option values from the same reference column.

The screenshot shows the 'Configure Form' window. It features a 'Governance Responsibilities' dropdown with 'Compliance Officer' selected. Below it is a 'Selected Roles Group' dropdown, also with 'Compliance Officer' selected. A 'List of Cities' dropdown is shown with 'Los Angeles' selected. At the bottom, a 'Selected City' radio button is selected for 'Los Angeles'.


Importing from Excel


You can import user-defined project properties from an XLSX file. You can either use an existing XLSX file or download an extended properties file from a project. Ensure that the XLSX file follows the correct template.

To import extended properties from XLSX files, follow these steps:

1. On the **Extended Properties** tab, click **Import From Excel**.

The Upload Excel page appears.



2. Click **Choose File**.
3. Browse and select the XLSX file.
4. Click .


The Upload Excel page appears. It displays the data in the XLSX file.

#	FIELD	VALUE	TYPE	PARENTFIELD	CREATED_BY	CREATED_DATE_TIME
#	Select Column To Import	Select Column To Import	Select Column To Import	Select Column To Import	Select Column To Import	Select Column To Import
1	Data Stewards		Combo Box			
2	Data Steward_UK	Data Steward_UK	Text Box	/Data Stewards	Administrator	10/20/2020 06:42:38
3	Data Steward_GER	Data Steward_GER	Text Box	/Data Stewards		
4	Data Owners	Data Owner_GER	Text Box		Administrator	10/20/2020 06:42:38

5. Double-click the **Select Column To Import** cell in the required column.

The available options appear.

Importing from Excel



#	FIELD	VALUE	TYPE	PARENTFIELD
#	Select Column To Import	Select Column To Import	Select Column To Import	Select Column To Import
1			Combo Box	
2	Data Steward_UK	Data Steward_UK	Text Box	/Data Stewards
3	Data Steward_GER	Data Steward_GER	Text Box	/Data Stewards


6. Select an appropriate option.

For example, if you select Field, then the selected column is imported as Field.

Similarly, you can also select the Value, Type, and Parentfield columns. Ensure that you at least select a Field column.

7. Click .

The extended properties are imported.



Configure Edit Delete Import From Excel Export To Excel

Form Values

Data Stewards Select an option

Data Owners Data Owner_GER

Technical Data Steward Tech Data Steward_GER

Compliance Officer Mapping Designer

Self Help

Adding Tasks

To improve productivity and collaboration, you can create tasks related to mapping projects. These tasks may be to-do tasks, access requests, or issues. With Action Center Settings, you can manage task types.

To add tasks, follow these steps:

1. In the **Workspace Mappings** pane, click a project.

The Mapping Summary page appears.


The screenshot shows the 'Mapping Summary' page. On the left, there is a 'Workspace Mappings' pane with a tree view showing 'erwinDIS (8)' selected. The main area displays a table of mapping projects. The table has the following columns: #, Project Name, Subject Hierarchy, Map Name, Lock Status, Locked By, Locked Date, Workflow Status, Mapping State, and Mapping Description. The data rows are as follows:

#	Project Name	Subject Hierarchy	Map Name	Lock Status	Locked By	Locked Date	Workflow Status	Mapping State	Mapping Description
1	erwinDIS		bb	🔒			Preliminary Draft	In Progress	
2	erwinDIS		BugTrial	🔒	Administrator	09/15/2020 08:48:48	Preliminary Draft	Approved	Testing for a b logged by QA
3	erwinDIS		Data Integration	🔒	Administrator	07/13/2021 03:23:42	Preliminary Draft	Approved	
4	erwinDIS		Demo	🔒			Preliminary Draft	In Progress	
5	erwinDIS		erwinSalesIntegration	🔒			Preliminary Draft	Approved	

2. Click the **My Action Center** tab.


The My Action Center tab opens. It displays a list of all tasks related to the project.

Adding Tasks



3. Click .

A list of task types appears. You can add or delete a task type from this list using [Action Center Settings](#).



4. Click the required task type.


The Create New Task page appears.

Adding Tasks


5. Enter appropriate values in the fields. Refer to the following table for field descriptions.

Field Name	Description
Task is being created on Asset	Specifies the asset for which the task is created. This field autopopulates with the project name.
With Task Type as	Specifies the task type. For example, To do Task.
Name	Specifies the name of the task. By default, it autopopulates with a name in the fol-

Adding Tasks

Field Name	Description
	Following format: Project_<Project_Name>. You can edit it and rename the task. For example, Test Mappings.
Description	Specifies a description of a task. For example: Test all the mappings and record the effort required.
Important	Specifies whether the task is important
Due	Specifies the due date of the task. Use  to set the due date.
Assign Users	Specifies the users assigned to the task. You can assign DI and BU users from the list. For example, Richard Cooper.
External user emails	Specifies the email ID of external users. For example, chris.harris@quest.com

6. Click .

The task is created and saved. Use  to edit the task details and attach relevant documents.

Chat

Use the Chat tab to send messages to the assigned and external users of a task.

On the **Chat** tab, enter your message in the text box and use the following options:

Assigned


Use this option to send messages to the assigned users.

External Users

Use this option to send messages to external users.

Users are notified via Messaging Center.

Adding Tasks



You can manage a task using the options available on the task list. [Managing a task](#) involves:


- Marking tasks complete
- Viewing task details
- Editing task details
- Disabling notifications
- Downloading Chat
- Sharing chat
- Marking tasks as pending
- Deleting tasks

With the My Action Center tab, you can filter and search tasks based on its status and assignments. For more information on search and filter mechanisms, refer to the [Filter and Search](#) topic.


Configuring Task Types


You can configure task types to categorize tasks. By default, three task types, To-Do Task, Request Access, and Issue are available. You cannot edit or delete these task types.

To configure task types, follow these steps:

1. In the utility section, click .

The Task Type Configuration pane appears. It displays a list of available task types.




2. In the Add New Task Type box, enter a new task type in the space provided and click .

The task type is added in the list of available tasks.

For example, in the following image, a task type, Schedule Job is added.

Configuring Task Types



Use the following options to manage task types:

Edit (✎)

Use this option to edit the task type.

Delete (🗑)

Use this option to delete a task type.

Managing Tasks


Managing tasks involves:

- Marking tasks complete
- Viewing task details
- Editing task details
- Disabling notifications
- Downloading Chat
- Sharing chat
- Marking tasks as pending
- Deleting tasks

To mark tasks complete, on the task list, for the required task, click the radio button.

The task is moved to the list of completed task.

For example, in the following image, the task, Add Business rule is marked complete.




To manage tasks, follow these steps:

1. In the task list, for the required task, click ⋮.

The available options appear.

Managing Tasks



2. Use the following options to work on tasks:

View Task Details

Use this option to view task details. These details include task name, description, assigned assets, attached documents, and so on.

Edit Task Details

Use this option to update task details.

Disable Notification

Use this option to stop receiving notifications related to a task. By default, notifications are enabled, and users assigned to task receive notifications.

Download Chat as Text


Use this option to download chat related to a task in the TXT format.


Send Chat as Email

Use this option to share the chat related to a task via an email. Click **Send Chat as Email**.

The Email Selection page appears. It displays a list of users assigned to the task.

Managing Tasks



Select the required users, and then click . An email is sent to the selected users.

Mark as Pending

This option is available for a completed task. Use this option to mark a task as pending.

To delete a task, in the task list, for the required task, click .



You can delete a task only if you have created the task.


Creating Subject Areas

Subject areas provide one more level of grouping for mapping specifications. You can create a subject area within a project or within another subject area. Ensure that the subject area names are unique under each project.

Subject Areas

To create subject areas, follow these steps:

1. In the **Workspace Mappings** pane, right-click a project.



2. Click **New Subject Area**.

The Add Subject page appears.

Creating Subject Areas

3. Enter the **Subject Name** and **Subject Description**.

For example:

- **Subject Name:** Members.
- **Subject Description:** This subject area is created to arrange the mappings logically.

You can use additional fields and define UI labels in [Language Settings](#).

4. Click .

The subject area is saved and added to the project.


Nested Subject Areas

You can create subject areas within another subject area. These subject areas are called nested subject areas.

To create nested subject areas, follow these steps:

Creating Subject Areas


1. In the **Workspace Mappings** pane, right-click a subject area.



2. Click **New Subject Area**.

The Add Subject page appears.

Creating Subject Areas



3. Enter the **Subject Name** and **Subject Description**.

You can use additional fields and define UI labels in [Language Settings](#).

4. Click .

A subject area is created under the subject area.

Once a subject area is created, you can enrich it further by [Tagging Subjects](#).


Managing Subject Areas

Managing subject areas involves:

- Deleting
- Reordering

To manage subject areas, follow these steps:

1. In the **Workspace Mappings** pane, right-click a subject area.



2. Use the following options:

Delete Subject Area


Use this option to delete subject areas that are not required.

Reorder Subject Areas

Use this option to reorder subject areas. To reorder subject areas, click **Reorder Subject Areas**.

The Subject for <Project_Name> page appears.

Managing Subject Areas



#	Subject Name	Current Order	New Order	Parent Hierarchy	Created By	Created Date	Modified By	Modified Date
1	L_Name[0]	1	1	A_Project	Administrator	2019-10-30 11:45:11.917	Administrator	2019-10-30 11:45:11.917
2	P_Name[0]	2	2	A_Project	Administrator	2019-10-30 11:44:51.983	Administrator	2019-10-30 11:44:51.983
3	S_Name[0]	3	3	A_Project	Administrator	2019-10-30 11:35:42.867	Administrator	2019-10-30 11:35:42.867

To order subject areas, from the **Order By** list, select one of the following options:

- **Ascending Order:** Select this option to order in ascending alphabetical order.
- **Descending Order:** Select this option to order in descending alphabetical order.
- **Custom Order:** Select this option to order in custom order.

To sort subject areas, from the **Sort Subjects By** list, select one of the following options:

- **Subject Name:** Select this option to sort by subject name.
- **Created By:** Select this option to sort by the users who created subject areas.
- **Created Date:** Select this option to sort by created date.
- **Modified By:** Select this option to sort by the users who modified subject areas.
- **Modified Date:** Select this to sort by the modified date.

Managing Projects


Managing projects involves:

- Uploading legacy maps
- Export mappings
- Export change logs
- Viewing reports
- Sharing links
- Deleting projects
- Viewing workflows

To manage projects follow these steps:

1. In the **Workspace Mappings** pane, right-click a project.

The available options appear.



Managing Projects

2. Use the following options:

Upload Legacy Maps

Use this option to upload maps in the XLSX format. Ensure that you use the required template.

Export All

Use this option to download the required maps in a project.

Export Change Log

Use this option to download change logs of all the maps in a project.

Reports

Use this option to download various reports related to a project.

Share Link

Use this option to share link of a project with your team members.

Delete Project

Use this option to delete a project.

View Workflow

Use this option to view workflow status of a project.


Defining Transformations

Transformations specify rules that derive values from source columns to get the required values in target columns. You can define enterprise-level and project-level transformations. These transformations can be used as business rules and extended business rule transformations in mapping specifications. Ensure that you define transformations for the same ETL option as that of your mapping project.

To define transformations, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click any one of the following:
 - **Transformations node:** Click this option to define enterprise-level transformations.
 - **Transformations node under a project:** Click this option to define project-level transformations.

For example, if you click the Transformations node, then the Transformation Details page appears.




#	Transformation Name	SSIS Pseudocode	Informatica Pseudocode	Intended Use
1	1-DataGov(HighDate:12/31/9999)		To_date(mm/dd/yyyy,12/31/9999)	DataGovernance r...
2	2-DataGov(LowDate01/01/0001)		To_date(mm/dd/yyyy, 01/01/0001)	DataGovernance r...
3	3-DataGov(AverageChurn)		Count(active customers)/(Count of Cancelled Customers for current month)	DataGovernance r. Churn KPIs are used.

3. Click .


The Transformation Rule Editor page appears.

Defining Transformations

4. Enter or select appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Published	Switch Published on () to publish the transformation.
Transformation Name	Specifies a unique name of the transformation. For example, ASCII.
Scope	Specifies the projects to which the transformation can be applied. For example, All Projects.
ETL Option	Specifies the ETL option. For example, Informatica Pseudocode. You can configure ETL option list and add or remove an ETL option from the list.

Defining Transformations

Field Name	Description
Replace Transformation Name with Pseudocode	Switch Replace Transformation Name with Pseudocode on () to replace the transformation name with pseudocode.
Pseudocode	Specifies the pseudocode for the transformation. Enter a pseudocode or use Ctrl + Space keys to select a pseudocode. For example, To_date(mm/dd/yyyy,1231,9999).
Intended Use	Specifies the objective of the transformation. For example: Data governance rule - use on projects.

5. Click .

A new transformation is added on the Transformations Details page.

You can upload transformations in bulk [using an MS Excel file](#).

Once a transformation is defined, you can manage it using the options available on right-clicking the transformation. [Managing Transformations](#) involves:

- Editing transformations
- Running impact analysis
- Viewing history

Configuring Transformation Library

You can create transformations for the following ETL options:


- DataStage Pseudocode
- BODS Pseudocode
- SSIS Pseudocode
- Informatica Pseudocode
- ODI Pseudocode
- Talend Pseudocode

This ETL options list forms the Transformation Library and is configurable. You can add or remove an ETL option from the ETL options list.

To configure transformation library, follow these steps:

1. In the **Workspace Mappings** pane, click the **Transformations** node.

The Transformation Details page appears.




#	Transformation Name	BODS Pseudocode	SSIS Pseudocode	Informatica Pseudocode	ODI Pseudocode	Talend Pseudocode
1	1-DataGov(HighDate:12/31/9999)			To_date(mm/dd/yyyy,12/31/9999)		
2	2-DataGov(LowDate01/01/0001)			To_date(mm/dd/yyyy,01/01/0001)		
3	3-DataGov(AverageChurn)			Count(active_customers)/(Count of Canceled Customers for current month)		

2. Click .

The ETL Settings page appears.

Configuring Transformation Library



3. Switch an **<ETL_Option>** key to **ON** to add the corresponding ETL option to the Transformation Library.

For example, switch **BODS Pseudocode** to **ON** to add BODS Pseudocode to the Transformation Library.

4. Click **Save**.

ETL options are added to the ETL Option list.

Configuring Transformation Library

The screenshot shows the 'Transformation Rule Editor' window. It features a dark title bar with standard window controls. The main area is white and contains several configuration fields:

- Published:** A toggle switch currently set to 'OFF'.
- Transformation Name*:** An empty text input field.
- Scope:** A dropdown menu with 'All Projects' selected.
- ETL Option:** A dropdown menu with a list of pseudocode options. The 'BODS Pseudocode' option is currently selected and highlighted in blue.
- Pseudocode:** A large, empty text area for entering the transformation logic.

Below the Pseudocode field, there is a note: "Note: Press 'Ctrl + Space' to select Transformations".

At the bottom left of the window, the text 'Intended Use' is visible.


Uploading Transformations

You can upload transformations in bulk using an MS Excel file. You can either use an existing MS Excel file or a template to upload transformations. Ensure that the MS Excel file follows the correct template.

To upload transformations, follow these steps:

1. In the **Workspace Mappings** pane, click the **Transformations** node.


The Transformation Details page appears.



#	Transformation Name	Informatica Pseudocode	Intended Use	Scope
1	1-DataGov(HighDate:12/31/9999)	To_date(mm/dd/yyyy,12/31/9999)	DataGovernance rule - use on all projects	All Projects
2	2-DataGov(LowDate01/01/0001)	To_date(mm/dd/yyyy, 01/01/0001)	DataGovernance rule - use on all projects	All Projects

2. Click .

The Upload Transformations page appears.



3. Drag and drop or use  to browse and select the MS Excel file.

You can use a template to upload transformations. For more information on downloading templates, refer to the [Downloading Templates](#) section.


4. Click .

The file is uploaded, and transformations are added to the Transformation Details page.

Downloading Templates

To download templates, follow these steps:

1. In the **Workspace Mappings** pane, right-click the **Transformations** node.



2. Click **Download Template**.

The template is downloaded in the XLSX format. You can update the MS Excel file with the required transformations.

Managing Transformations


Managing transformations involves:

- Editing transformations
- Deleting transformations
- Running impact analysis
- Viewing history

To manage transformations, follow these steps:

1. In the **Workspace Mappings** pane, click the **Transformations** node.

The Transformation Details page appears.



#	Transformation Name	BODS Pseudocode	SSIS Pseudocode	Informatica Pseudocode	ODI Pseudocode	Talend Pseudocode
1	1-DataGov(HighDate:12/31/9999)			To_date(mm/dd/yyyy,12/31/9999)		
2	2-DataGov(LowDate01/01/0001)			To_date(mm/dd/yyyy, 01/01/0001)		
3	3-DataGov(AverageChurn)			Count(active customers)/(Count of Cancelled Customers for current month)		

2. Select the required row and right-click it.

The available options appear.

Managing Transformations

Transformation Details			
#	Transformation Name	BODS Pseudocode	SSIS Pseudocode
	<input type="text"/>	<input type="text"/>	<input type="text"/>
31	LAST		
32	FIRST		
33	FLOOR		
34	FV		
35	GET_DATE_PART		

Edit Transformation Details

Delete

Impact Analysis Report

History

3. Use the following options:

Edit Transformation Details

Use this option to edit transformation details, such as transformation name and its scope.

Delete

Use this option to delete the selected transformation.



If a transformation is already used in a Mapping Specification, it is still visible under it. However, it is not available for future use.

Impact Analysis Report


Hover over **Impact Analysis Report** and use the following options to view impact analysis of transformations:

Default Search: Use this option to view the impact analysis report of the selected transformation.

Advanced Search: Use this option to select multiple transformations and view their impact analysis report.

For example, the following image displays the impact analysis of a transformation.

Managing Transformations



Advanced Search

Business Rule: LOWER

Impact Analysis Report

#	Project Name	Mapping Name	Map Specification Version	Business Rule
1	TestData Map	HeteroMultiSrc_Lookup_BR	1.0	LOWER(#1)
2	TestData Map	HeteroMultiSrc_Lookup_BR	1.0	LOWER(#1)
3	TestData Map	HomoMultiSrc_Lookup_BR	1.0	LOWER(#1)
4	TestData Map	HomoMultiSrc_Lookup_BR	1.0	LOWER(#1)
5	TestData Map	MultiSource_Lookup_BusRt	1.0	LOWER(#1)
6	TestData Map	SingleSource_Lookup_BusF	1.0	LOWER(#1)
7	Lineage Demo	Account_Tableau_Report	1.0	LOWER(%1)

History

Use this option to view activity logs of a transformation.

For example, the following image displays the history of a transformation.

Managing Transformations

History							
#	Transformation Name	Pseudocode	Intended Use	Created By	Created Date Time	Last Modified By	Last Modified Date
1	FLOOR		ETL Built-In Transformation: Record handling and processing rule for all projects. Returns the largest integer less than or equal to the numeric value you pass to this function. For example, if you pass 3.14 to FLOOR, the function returns 3. If you pass 3.98 to FLOOR, the function returns 3. Likewise, if you pass -3.17 to FLOOR, the function returns -4.	Administrator	2018-09-14 10:39:48.937	Administrator	2020-16:23

Creating Maps


You can create maps under a project or subject area. You can perform source to target mappings and create mapping specifications in maps. These mapping specifications facilitate your data integration project.

To create maps, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, right-click a project or subject area.

Creating Maps

For example, when you right-click a project the available options appear.



3. Click **New Map**.

The Create a New Mapping page appears.

Creating Maps

4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Mapping Name	Specifies the mapping specification name. For example, EDW_PROD_IDS_Benefits_Detail. For more information on naming conventions, refer to the Best Practices section.
Mapping Version	Specifies the version of the mapping specification. This field is autopopulated. For example, 1.00. For more information on configuring version display of maps, refer to the Configuring Version Display topic.
Sync Source	Specifies whether source metadata syncs with the mapping.


Creating Maps

Field Name	Description
Metadata	Switch Sync Source Metadata to ON to sync source metadata with the mapping.
Sync Target Metadata	Specifies whether target metadata syncs with the mapping. Switch Sync Target Metadata to ON to sync target metadata with the mapping.
Mapping Description	Specifies the description of the mapping. For example: This is a map between EDW source and IDS target systems.
Mail Comments	Specifies the mail comments, which can be sent to the project users through an email notification. For example: Source and target have identical columns, hence they can be mapped using auto-map technique. For more information on configuring notifications, refer to the Configuring Notifications topic.

5. Click **Finish** or **Proceed with Auto Map**.

When you click Finish, a map is created and saved in the mappings tree. You can create a mapping specification under the map using [drag and drop method](#) or [graphical design](#).

Creating Maps



When you click Proceed with Auto Map, you can [create mapping specification using auto-map technique](#).

Creating Maps

Auto Map Source & Target Objects

Mapping Groups: Add Group, Delete Group, Ranking Threshold: 50%, Number of Recommendations: 50

View All, Group 1

Source Object(s), Target Object(s)

Auto Mapping Preview Grid

#	Source System	Source Environment	Source Object	Source Attribute	Source Logical Name	Target Attribute	Target Logical Name	Target Object	Target Environment	Target
	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>

Self Help

Also, You can assign one or multiple tags to maps. For more information on tagging maps, refer to the [Tagging Maps](#) topic.

Drag and Drop

You can map source metadata with target metadata and create mapping specifications using the drag and drop method. This method is useful even when source column names are different from target column names. After mapping source to target, you can set a [target update strategy](#) for the mappings and enter a description for the strategy.

You can drag and drop tables or columns into the mapping specifications using one of the following:


- [Metadata Search View](#)
- [Metadata Tree View](#)

Creating Mapping Specifications using Metadata Search View

To create mapping specifications using drag and drop method, follow these steps:

1. In the **Workspace Mappings** pane, click a map.

By default, the Mapping Specification tab opens.



2. Click .


The Mapping Specification grid switches to edit mode.

You can use the Metadata Search View pane to drag and drop the required source table or column into the Mapping Specification grid. The Metadata Search View pane displays technical assets in a hierarchical manner similar to the Metadata Manager.

Drag and Drop

The screenshot shows a software interface with two tabs: 'Metadata Tree View' and 'Metadata Search View'. The 'Metadata Search View' is active, displaying a search results page. At the top, there is a search bar with a magnifying glass icon and a dropdown arrow. Below the search bar, the word 'Metadata' is displayed in blue. A grey bar highlights the word 'Systems' in orange. Underneath, the word 'Search' is displayed in blue. A horizontal line separates the search results from the rest of the page. The search results are a list of system names, each followed by a blue chevron icon pointing to the right. The list includes: erwin DI Suite, erwin DM, High Tower, Informatica, Oracle, Salesforce, SAP, Snowflake, SQL System, SQLTechPubs, TABLEUAU, TALEND, and To be deleted.

System Name	Action
erwin DI Suite	>
erwin DM	>
High Tower	>
Informatica	>
Oracle	>
Salesforce	>
SAP	>
Snowflake	>
SQL System	>
SQLTechPubs	>
TABLEUAU	>
TALEND	>
To be deleted	>

Alternatively, click  to open **Metadata Search** page. This page enables you to search for tables or columns in the metadata by selecting appropriate values.

Drag and Drop

Metadata Search


Select System: erwin DM | Select Environment: DM Landing | Select Table: All | Enter Column Name: | SEARCH

erwin DM → DM Landing → All


#	Table Name	Column Name	Table Definition	Table Comments	Logical Table Name	Logical Column Name	Column Definition
1	Citizens	CitizenID			Citizens	CitizenID	
2	Citizens	CitizenName			Citizens	CitizenName	
3	Citizens	EmployeeeID			Citizens		
4	Employees	EmployeeName			Employees	EmployeeName	
5	Employees	EmployeeeID			Employees	EmployeeeID	

- Expand a parent node to view its assets, and select the required asset.
For example, open a system node to view relevant environments in it. Then, expand the environment node to view tables and columns respectively.

Drag and Drop



Additionally, the search bars in the Metadata Search View enables you to search for specific environments, tables, or columns.

Hover over a table or a column and click  to open **Metadata Properties** page. This page displays business, technical, and extended properties of the selected asset.

Drag and Drop

4. Drag the selected source table or column from the **Metadata Search View** pane and drop in the **Mapping Specification** grid.

Ensure that you drop source tables or columns under the respective columns.



You cannot drop source systems or environments in the Mapping Specification grid.

The screenshot shows the Mapping Specification grid with the following columns: Source Column Name, Source Column Identity Flag, Source Column Nullable Flag, Source Percent Null Value, Source Natural Key Flag, Source Primary Key Flag, Source Logical Column, Source SDI Flag, Source SDI Description, and Source Column. The grid contains several rows of source columns, including Account_ATM_Stz, Account_Cash_On, Account_Producti (checked), Cash_On_Delivery, No_of_Records_A (checked), and others. The Metadata Search View pane on the right shows the Metadata Tree View with the path Metadata > erwin DM > DM Landing. The Tables section is expanded, showing Citizens and Employees. The Columns section is also expanded, showing CitizenID, CitizenName, and EmployeeID.

5. Similarly, drag the target table or column from the **Metadata Search View** pane and drop in the **Mapping Specification** grid.

Ensure that you drop target tables or columns under the respective columns.

6. Click .

The mapping specification is saved.


Creating Mapping Specifications Using Metadata Tree View

To create mapping specifications using drag and drop method, follow these steps:

Drag and Drop

1. In the **Workspace Mappings** pane, click a map.

By default, the Mapping Specification tab opens.



2. Click .


You can now edit the Mapping Specification grid.

3. Drag the selected source table or column from the **Metadata Tree View** pane and drop in the **Mapping Specification** grid.

Ensure that you drop source tables or columns under the respective columns.




You cannot drop source systems or environments in the Mapping Specification grid.



Alternatively, click  to use the search function on the Metadata Tree View pane to

Drag and Drop

locate the required asset in the list.



4. Drag the selected target table or column from the **Metadata Tree View** pane and drop in the **Mapping Specification** grid.

Ensure that you drop target tables or columns under the respective columns.



You cannot drop target systems or environments in the Mapping Specification grid.

5. Click .

The mapping specification is saved.

Setting Target Update Strategy


To set the target update strategy, follow these steps:

1. Expand the **Additional Mapping Information** pane and click the **Target Update Strategy** tab.

This pane is available at bottom of the central pane when you click a map in the Workspace Mappings pane.

Drag and Drop

2. On the **Target Update Strategy** tab, click .



3. Click the required strategy, enter **Update Strategy Description**, and click .
The target update strategy is set.

4. Click .

The source to target mapping is saved.

You can enrich a mapping specification by:

- [Adding transformation and lookup details](#)
- [Associating code cross walks \(code mappings\)](#)
- [Associating reference tables](#)
- [Linking requirements](#)

After creating a mapping specification, you can analyze a mapping specification. [Analyzing mapping specifications](#) involves:

- Generating virtual preview of target
- Previewing data
- Performing table gap analysis
- Performing column gap analysis
- Running impact analysis

Drag and Drop

- Running lineage analysis
- Running end to end lineage
- Opening business view
- Viewing mapping statistics

Graphical Designer

You can use the Graphical Designer tab to map source metadata with target metadata and create mapping specifications. This method is useful even when source column names are different from target column names. After mapping source to target, you can set a [target update strategy](#) for the mappings and enter a description for the strategy.

You can create mapping specifications in the Graphical Designer tab using one of the following:


- [Metadata Search View](#)
- [Metadata Tree View](#)

Creating Mapping Specifications using Metadata Search View

To create mapping specifications graphically, follow these steps:


1. In the **Workspace Mappings** pane, click a map.

By default, the Mapping Specification tab opens.



2. Click the **Graphical Designer** tab.

The following page appears.





Graphical Designer

3. Click .

The Graphical Designer tab switches to edit mode.

You can use the Metadata Search View pane to drag and drop the required source table or column into the Graphical Designer. The Metadata Search View pane displays technical assets in a hierarchical manner similar to the Metadata Manager.



Alternatively, click  to open **Metadata Search** page. This page enables you to search for tables or columns in the metadata by selecting appropriate values.

Graphical Designer

Metadata Search

Select System: erwin DM | Select Environment: DM Landing | Select Table: All | Enter Column Name: | SEARCH

erwin DM → DM Landing → All

#	Table Name	Column Name	Table Definition	Table Comments	Logical Table Name	Logical Column Name	Column Definition
1	Citizens	CitizenID			Citizens	CitizenID	
2	Citizens	CitizenName			Citizens	CitizenName	
3	Citizens	EmployeeeID			Citizens		
4	Employees	EmployeeName			Employees	EmployeeName	
5	Employees	EmployeeeID			Employees	EmployeeeID	

- Expand a parent node to view its assets, and select the required asset.
For example, open a system node to view relevant environments in it. Then, expand

Graphical Designer

the environment node to view tables and columns respectively.

Metadata Search View

Metadata > erwin DI Suite >
erwin_Sales

Tables

Search

dbo.RM_RESOURCE_New

Columns

Search


RESOURCEID_New
RESOURCENAME_New
RESOURCEDESC_New

Graphical Designer

Alternatively, the search bars in the Metadata Search View enables you to search for specific environments, tables, or columns.

Hover over a table or a column and click **i** to open **Metadata Properties** page. This page displays business, technical, and extended properties of the selected asset.


5. Drag the selected source table from the **Metadata Search View** pane and drop on the **Graphical Designer** tab.
6. On the **Graphical Designer** tab, select the source table and click **▼** next to the Auto Map option. Then, select **As Source** option to specify the table as source.



7. Similarly, drag target table from the **Metadata Search View** pane and drop on the **Graphical Designer** tab.

Graphical Designer

8. On the **Graphical Designer** tab, select the target table and click ▼ next to the Auto Map option. Then, select **As Target** to specify the table as target.




Graphical Designer

9. Use the following options to map source with target:

- If the source and target have same column names, click **Auto Map**.


The source and target columns are mapped.



- If the source and target have different column names, then click and drag your mouse from a source column to the required target column.

Graphical Designer

The source and target columns are mapped. Repeat the process for the required assets.



10. Click .

The mapping specification is saved.


Creating Mapping Specifications using Metadata Tree View

To create mapping specifications graphically, follow these steps:

1. In the **Workspace Mappings** pane, click a map.


By default, the Mapping Specification tab opens.



Graphical Designer



2. Click the **Graphical Designer** tab.

The following page appears.






3. Click .
4. Drag the selected source table from the **Metadata Tree View** pane and drop on the **Graphical Designer** tab.
Alternatively, click  to use the search function on the Metadata Tree View pane to

Graphical Designer


locate the required asset in the list.


Metadata Tree View

- Metadata
 - erwin DI Suite
 - _Local (v1.01)
 - erwin_Sales (v1.00)
 - dbo.RM_RESOURCE_New
 - RESOURCEID_New
 - RESOURCENAME_New
 - RESOURCEDESC_New
 - RESOURCECELLPHONE_New**
 - RESOURCEHOMEPHONE_New
 - RESOURCEEMAIL_New

Graphical Designer


5. On the **Graphical Designer** tab, select the source table and click  next to the Auto Map option. Then, select **As Source** option to specify the table as source.



6. Drag the selected target table from the **Metadata Tree View** pane and drop on the **Graphical Designer** tab.

Graphical Designer


7. On the **Graphical Designer** tab, select the target table and click ▼ next to the Auto Map option. Then, select **As Target** to specify the table as target.



8. Use the following options to map source with target:
 - If the source and target have same column names, click **Auto Map**.

Graphical Designer


For example, the following image displays the source and target columns are mapped automatically.



- If the source and target have different column names, then click and drag your mouse from a source column to the required target column.

Graphical Designer

For example, the following image displays the source and target columns (blue and red arrows) that are mapped manually.



9. Click .

The mapping specification is saved.

Setting Target Update Strategy


To set the target update strategy, follow these steps:

1. Expand the **Additional Mapping Information** pane and click the **Target Update Strategy** tab.

This pane is available at bottom of the central pane when you click a map in the Graphical Designer tab.

Graphical Designer

2. On the **Target Update Strategy** tab, click .



3. Click the required strategy, enter **Update Strategy Description**, and click .

The target update strategy is set for the mapping specification.

4. Click .

The source to target mapping is saved.

You can enrich a mapping specification by:

- [Adding transformation and lookup details](#)
- [Associating code cross walks \(code mappings\)](#)
- [Associating reference tables](#)
- [Linking requirements](#)

After creating a mapping specification, you can analyze a mapping specification. [Analyzing mapping specifications](#) involves:

- Generating virtual preview of target
- Previewing data
- Performing table gap analysis
- Performing column gap analysis
- Running impact analysis

Graphical Designer

- Running lineage analysis
- Running end to end lineage
- Opening business view
- Viewing mapping statistics

Auto-Map


Starting erwin Data Intelligence (erwin DI) v12.1, you can use the auto-map feature to create mapping specifications even when source and target column names do not match. With this feature, you can view recommended matches for a source column and select the most appropriate target column.

Creating Mapping Specifications

To create mapping specifications using auto-map, follow these steps:

1. In the **Workspace Mappings** pane, right-click a project or subject area.

The available options appear.



2. Click **New Map**.

The Create New Mapping page appears.

Auto-Map

Create a New Mapping

Mapping Name*

Mapping Version

Version Label

Sync Source Metadata

Sync Target Metadata

Job Name XRef


Mapping Description

Mail Comments

Self Help


3. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. For field description, refer to the [Creating Maps](#) topic.
4. Click **Proceed with Auto Map**.
The Auto Map Source & Target Objects page appears.
5. Drag the target table from the **Metadata** pane and drop it in the **Target Object(s)** box.
You can add more than one target tables.

Auto-Map



6. Drag source table from the **Metadata** pane and drop it in the **Source Object(s)** box.

You can add more than one source tables.



7. Click .

The Auto Mapping Preview Grid displays a list of recommended matches (target columns) for each source column based on maximum matching score. In case the recommended match is not suitable, you can evaluate more recommendations and [assign targets manually](#).

Auto-Map

Auto Map Source & Target Objects

Mapping Groups: **Add Group** **Delete Group** Ranking Threshold: Number of Recommendations:

View All
EmployeeTerritories_Em...

Source Object(s)

- dbo.EmployeeTerritories
- dbo.Employees

Target Object(s)

- dbo.EmployeeTerritories
- dbo.Employees

Auto Mapping Preview Grid

#	Source System	Source Environment	Source Object	Source Attribute	Target Attribute	Target Object	Target Environment	Target System	Total Recommendations
5	QuestHR	QuestPayroll	dbo.Employees	City	City	dbo.Employees	AdvancePayroll	QuestPayroll	2
6	QuestHR	QuestPayroll	dbo.Employees	Country	Country	dbo.Employees	AdvancePayroll	QuestPayroll	2
7	QuestHR	QuestPayroll	dbo.Employees	EmployeeID	EmployeeIDNu	dbo.Employees	AdvancePayroll	QuestPayroll	3

Total Rows: 21 | Target Tables: 2 | Source Tables: 2 | Targets Not Mapped: 1 | Sources Not Mapped: 1

Create a distinct Mapping for every Group

8. Use the following options to manage the auto-map recommendations:

Ranking Threshold

Use this option to set the threshold for match scores. Matches with scores below this threshold do not appear as recommendations. By default, it is set to $\geq 50\%$, which means that matches with scores below 50% are not recommended.

Number of Recommendations

Use this option to limit the number of recommendations. By default, it is set to ≤ 50 , which means that number of recommended matches cannot exceed 50.

Maximize (🔍)

Use this option to maximize or minimize the Auto Mapping Preview Grid.

Delete Orphan Sources (🗑️)

Use this option to delete source attributes that are not mapped.

Delete Orphan Targets (🗑️)

Use this option to delete target attributes that are not mapped.

Auto-Map

Add Transformations (T)

Use this option to [add transformations](#) for the auto map. You can add business rule, extended business rule transformation, look up reference column, lookup on, and trans look up condition.

Add Group

Use this option to add a mapping group to perform other mappings.

Rename Mapping Group (R)

Use this option to rename a mapping group.

Delete Group

Use this option to delete a mapping group. To delete a mapping group, click the mapping group and then click **Delete Group**.

Create a distinct Mapping for every Group

Use this option to create distinct mapping for every group.

9. Click **Finish**.

A new map is created and saved under the Mappings tree. All the auto-maps in the multiple mapping groups appear in the same sequence in the Mapping Specification grid.

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision	Target Column Scale	Target Column Nullable Flag	Target Column ETL Default Value
1	QuestPayroll	AdvancePayroll	dbo.EmployeeTerr	EmployeeID	int	10	10	0	<input type="checkbox"/>	
2	QuestPayroll	AdvancePayroll	dbo.EmployeeTerr	TerritoryID	nvarchar	20	0	0	<input type="checkbox"/>	
3	QuestPayroll	AdvancePayroll	dbo.Employees	ResidentialAddress	nvarchar	60	0	0	<input checked="" type="checkbox"/>	
4	QuestPayroll	AdvancePayroll	dbo.Employees	DateofBirth	datetime	23	23	3	<input checked="" type="checkbox"/>	


Assigning Targets Manually

Auto-Map

In the Auto Mapping Preview Grid, the **Total Recommendations** column displays the number of mapping recommendations. To view the recommendations for required rows, click the corresponding number.

The Total Recommendations on page appears. It displays the recommended matches for the source column. By default, a match with the highest score is selected.

For example, the following image displays the recommended matches for a source column, EmployeeID.



You can reject the default match and select another recommended match. To select a match, click the required radio button, and then click **Assign As Target**.

Setting Target Update Strategy


To specify target update strategy, follow these steps:

1. Expand the **Additional Mapping Information** pane.

This pane is available at the bottom of the central pane on clicking a map in the Workspace Mappings pane.

2. Click the **Target Update Strategy** tab.

Auto-Map



3. Click .

4. Click the required strategy, enter **Update Strategy Description**, and click .

The target update strategy is configured.


Adding Transformations

You can add transformations to an auto-map and specify whether it is applicable to exact match, orphan source, orphan target, or all the rows.

To add transformations in auto-maps, follow these steps:

1. Under the **Auto Mapping Preview Grid**, click .

The Auto Map Transformation page appears.



2. Click .

A row is added to the grid.


3. Double-click the cell under the **Key** column and select the required transformation.

Auto-Map

4. Double-click the cell under the **Value** column and select a value.



You can use transformations created under the Transformations node only for Business Rule. For other transformations, enter the required value.



5. Use the following options:

Exact Match

Use this option to apply the transformation on the exactly matched rows in the Auto Mapping Preview Grid.

Orphan Source

Use this option to apply the transformation on the orphan source rows in the Auto Mapping Preview Grid.

Orphan Target

Use this option to apply the transformation on the orphan target rows in the Auto Mapping Preview Grid.

All

Use this option to apply the transformation on every row in the Auto Mapping Preview Grid.

6. Click .

The transformations are added to the auto map.

You can enrich a mapping specification by:

Auto-Map

- [Adding transformation and lookup details](#)
- [Associating code cross walks \(code mappings\)](#)
- [Associating reference tables](#)
- [Linking requirements](#)

After creating a mapping specification, you can analyze a mapping specification. [Analyzing mapping specifications](#) involves:

- Generating virtual preview of target
- Previewing data
- Performing table gap analysis
- Performing column gap analysis
- Running impact analysis
- Running lineage analysis
- Running end to end lineage
- Opening business view
- Viewing mapping statistics

One to Many and Many to Many Mapping Specifications

You can map multiple source columns to single or multiple target columns to create a mapping specification. After mapping source to target, you can set a [target update strategy](#) for the mappings and enter a description for the strategy.

You can create mapping specifications in the Graphical Designer tab using one of the following:


- [Metadata Search View](#)
- [Metadata Tree View](#)

Creating Mapping Specifications Using Metadata Search View

To create one to many or many to many mapping specifications, follow these steps:

1. In the **Workspace Mappings** pane, click a map.

By default, the Mapping Specification tab opens.



2. Click .


The Mapping Specification grid switches to edit mode.

3. Switch  to **ON**.

The append mode is enabled. You can now drop multiple columns from the Metadata Search View pane in one row of the Mapping Specification grid.


You can use the Metadata Search View pane to drag and drop the required source table or column in the Mapping Specification grid. The Metadata Search View pane displays technical assets in a hierarchical manner similar to the Metadata Manager.

One to Many and Many to Many Mapping Specifications



The screenshot shows a web interface with two tabs: "Metadata Tree View" (active) and "Metadata Search View". Below the tabs, there are sections for "Metadata" and "Systems". The "Systems" section is highlighted in grey and contains a "Search" input field. Below the search field is a list of systems, each with a blue chevron icon to its right:

System Name	Action
erwin DI Suite	>
erwin DM	>
High Tower	>
Informatica	>
Oracle	>
Salesforce	>
SAP	>
Snowflake	>
SQL System	>
SQLTechPubs	>
TABLEUAU	>
TALEND	>
To be deleted	>

Alternatively, click  to open **Metadata Search** page. This page enables you to search for tables or columns in the metadata by selecting appropriate values.

One to Many and Many to Many Mapping Specifications

Metadata Search

Select System: erwin DM | Select Environment: DM Landing | Select Table: All | Enter Column Name: | SEARCH



erwin DM → DM Landing → All

#	Table Name	Column Name	Table Definition	Table Comments	Logical Table Name	Logical Column Name	Column Definition
1	Citizens	CitizenID			Citizens	CitizenID	
2	Citizens	CitizenName			Citizens	CitizenName	
3	Citizens	EmployeeeID			Citizens		
4	Employees	EmployeeName			Employees	EmployeeName	
5	Employees	EmployeeeID			Employees	EmployeeeID	

- Expand a parent node to view its assets, and select the required asset.
For example, open a system node to view relevant environments in it. Then, expand

One to Many and Many to Many Mapping Specifications

the environment node to view tables and columns respectively.

Metadata Search View  

Metadata > **erwin DI Suite** >
erwin_Sales

Tables

Search

dbo.RM_RESOURCE_New

Columns

Search


RESOURCEID_New

RESOURCENAME_New

RESOURCEDESC_New

One to Many and Many to Many Mapping Specifications


Alternatively, use the search bars in the Metadata Search View to search for specific environments, tables, or columns.

Hover over a table or a column and click  to open **Metadata Properties** page. This page displays business, technical, and extended properties of the selected asset.


5. Drag one or multiple source columns from the **Metadata Search View** pane in the **Mapping Specification** grid under the **Source Columns Name** column.

One to Many and Many to Many Mapping Specifications

You can use the Ctrl key to select multiple columns in the Metadata Search View pane.




One to Many and Many to Many Mapping Specifications

6. Similarly, drag single or multiple target columns from **Metadata Search View** in **Mapping Specification** under the **Target Columns Name**.
7. Click .

The mapping specification is saved.

You can view the mapping specification on the **Graphical Designer** tab to view the graphical representation of the one to many mappings.



Creating Mapping Specifications Using Metadata Tree View

To create one to many or many to many mapping specifications, follow these steps:

1. In the **Workspace Mappings** pane, click a map.

By default, the Mapping Specification tab opens.

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision	Target Column Scale	Target Column Nullable Flag	Target Column Name
---	--------------------	-------------------------	-------------------	--------------------	-------------------------	----------------------	-------------------------	---------------------	-----------------------------	--------------------

2. Click .


One to Many and Many to Many Mapping Specifications

3. Switch **APPEND OFF** to **ON**.

The append mode is enabled. You can now drop multiple columns from the Metadata Tree View pane in one row of the Mapping Specification grid.

4. Drag one or multiple source columns from the **Metadata Tree View** pane in the **Mapping Specification** grid under the **Source Columns Name** column.


You can use the Ctrl key to select multiple columns in the Metadata Tree View pane.




Alternatively, click  to use the search function on the Metadata Tree View pane to

One to Many and Many to Many Mapping Specifications

locate the required asset in the list.




5. Similarly, drag single or multiple target columns from **Metadata Tree View** in **Mapping Specification** under the **Target Columns Name**.
6. Click .

The mapping specification is saved.


One to Many and Many to Many Mapping Specifications


You can view the mapping specification on the **Graphical Designer** tab to view the graphical representation of the one to many mappings.



Setting Target Update Strategy

To set target update strategy, follow these steps:

1. Expand the **Additional Mapping Information** pane and click the **Target Update Strategy** tab.
2. On the **Target Update Strategy** tab, click .



3. Click the required strategy, enter **Update Strategy Description**, and click .

One to Many and Many to Many Mapping Specifications

4. Click .

The source to target mapping is saved.

You can enrich a mapping specification by:

- [Adding transformation and lookup details](#)
- [Associating code cross walks \(code mappings\)](#)
- [Associating reference tables](#)
- [Linking requirements](#)

After creating a mapping specification, you can analyze a mapping specification. [Analyzing mapping specifications](#) involves:

- Generating virtual preview of target
- Previewing data
- Performing table gap analysis
- Performing column gap analysis
- Running impact analysis
- Running lineage analysis
- Running end to end lineage
- Opening business view
- Viewing mapping statistics

Adding Transformation and Lookup Details

You can add transformation and lookup details to a mapping specification in the Mapping Specification grid.

Adding transformation details involves setting up:

- Business rule
- Extended business rule transformation

Ensure that you define business rules under the Transformations node for the same ETL Option as the Project ETL. For more information on defining business rules, refer to the [Defining Transformations](#) section.

Adding lookup details involves setting up:

- Trans lookup condition
- Lookup reference column
- Lookup on

Ensure that you scan the required table in the Metadata Manager to set trans lookup condition.

Adding Transformation Details

To add business rules to mapping specifications, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click a map.

By default, it opens the Mapping Specification tab.

Adding Transformation and Lookup Details

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision	Target Colour Scale
1	Erwin_Sales_Target	Integration_Target	dbo.RM_RESOURCE	RESOURCEID_New	int	4	10	0
2	Erwin_Sales_Target	Integration_Target	dbo.RM_RESOURCE	RESOURCENAME	varchar	100	0	0
3	Erwin_Sales_Target	Integration_Target	dbo.RM_RESOURCE	RESOURCEDESC_N	varchar	150	0	0

- Right-click the header menu of the **Mapping Specification** grid.

#	Source System Name	Source Environment Name	Source Table Name	Source Column Name	Source Column Data Type	Source Column Length	Business Rule
1	Erwin_Sales	Integration	dbo.RM_RESOURCE	RESOURCEID	int	4	
2	Erwin_Sales	Integration	dbo.RM_RESOURCE	RESOURCENAME	varchar	100	
3	Erwin_Sales	Integration	dbo.RM_RESOURCE	RESOURCEDESC	varchar	150	

- Select the **Business Rule** check box.

The Business Rule column is now available in the Mapping Specification grid.

- Click .

You can now edit the Mapping Specification grid.

- Double-click the cell under the **Business rule** column for the required source column. The available transformations appear.

Adding Transformation and Lookup Details

Segment	Source Table Name	Source Column Name	Source Column Data Type	Source Column Length	Business Rule	Extended Business Rule Transformation
Function	dbo.RM_RESOURCE	RESOURCEID	int	4		
Function	dbo.RM_RESOURCE	RESOURCENAME	varchar	100	1-DataGov(HighDate:12/31/9999) 2-DataGov(LowDate01/01/0001) 3-DataGov(AverageChurn)	
Function	dbo.RM_RESOURCE	RESOURCEDESC	varchar	150	ABORT ABS ADD_TO_DATE	
Function	dbo.RM_RESOURCE	RESOURCECELLPH	varchar	15		

7. Select a business rule.

You can add business rules for multiple source columns.

8. Click .

The business rules are added to the mapping specification.

To add extended business rule transformations, follow these steps:

1. Right-click the header menu of the **Mapping Specification** grid.

#	Source System Name	Source Environment Name	Source Table Name	Source Column Name	Source Column Data Type	Source Column Length	Business Rule
1	Erwin_Sales	Integration	dbo.RM_RESOURCE	RESOURCEID			
2	Erwin_Sales	Integration	dbo.RM_RESOURCE	RESOURCENAME			
3	Erwin_Sales	Integration	dbo.RM_RESOURCE	RESOURCEDESC	varchar	150	

2. Select the **Extended Business Rule Transformation** check box.

Adding Transformation and Lookup Details


The Extended Business Rule Transformation column is now available in the Mapping Specification grid.

3. Click .

You can now edit the Mapping Specification grid.


4. Click .

The available options appear.




5. Select the **Extended Business Rule** check box.
6. In the **Mapping Specification** grid, double-click the cell under the **Extended Business rule Transformation** column for the required source column.

The Extended Transformation Rule Editor page appears.




7. Select a pseudocode based on the Project ETL.
For example, if the Project ETL is Informatica then select Informatica Pseudocode.


Adding Transformation and Lookup Details



8. Press Ctrl + Space keys.

The available transformations appear.



If the required transformation is not available in the list, use  to create and update the transformations list.

9. Double-click the required transformation.

You can use  to replace the transformation name with the pseudocode.

10. Click .

The extended business rule transformation is added to the source column. You can add extended business rule transformation to multiple source columns. You can also


Adding Transformation and Lookup Details

configure UI labels for user defined fields. For more information on configuring UI labels, refer to the [Configuring Language Settings](#) topic.


Adding Lookup Details

To add lookup details in mapping specifications, follow these steps:

1. Right-click the header menu of the mapping specification grid.
2. Select **Lookup Reference Column**, **Lookup On**, and **Trans Lookup Condition**.



3. Drag the required table from the **Metadata Tree View** pane and drop it under the **Trans Lookup Condition** column for the required source column.



A SQL query populates.

Once trans lookup condition is set for the source column, you can add lookup reference column and lookup on.

Adding Transformation and Lookup Details

To add lookup reference column, double-click the cell under the **Lookup Reference Column** column and select the required option.

The screenshot shows a table with the following columns: Created By, Created Date, Lookup Reference Column, Lookup On, Trans Lookup Condition, Last Modified By, and Last Modified Date. The 'Lookup Reference Column' column is currently being edited, with a dropdown menu open showing options: ID, SOURCE_OBJECT_ID, SOURCE_OBJECT_TYPE_ID, TARGET_OBJECT_ID, TARGET_OBJECT_TYPE_ID, and RELATIONSHIP_DETAIL_ID. The 'Trans Lookup Condition' column contains a SQL query: SELECT ID, SOURCE_OBJECT_ID, SOURCE_OBJECT_TYPE_ID, TARGET_OBJECT_ID, TARGET_OBJECT_TYPE_ID, RELATIONSHIP_DETAIL_ID FROM dbo.ADS_ASSOCIATION.

Created By	Created Date	Lookup Reference Column	Lookup On	Trans Lookup Condition	Last Modified By	Last Modified Date
Administrator	2020-01-12 20:40:27.5			SELECT ID, SOURCE_OBJECT_ID, SOURCE_OBJECT_TYPE_ID, TARGET_OBJECT_ID, TARGET_OBJECT_TYPE_ID, RELATIONSHIP_DETAIL_ID FROM dbo.ADS_ASSOCIATION	Administrator	2020-01-12 20:40:27.5
Administrator	2020-01-12 20:40:27.5	ID			Administrator	2020-01-12 20:40:27.5
Administrator	2020-01-12 20:40:27.5				Administrator	2020-01-12 20:40:27.5

To add lookup on, double-click the cell under the **Lookup On** column and select the required option.

The screenshot shows the same table as above, but now the 'Lookup On' column is being edited. The dropdown menu is open, showing options: ID, SOURCE_OBJECT_ID, SOURCE_OBJECT_TYPE_ID, TARGET_OBJECT_ID, TARGET_OBJECT_TYPE_ID, and RELATIONSHIP_DETAIL_ID. The 'Trans Lookup Condition' column remains the same as in the previous screenshot.

Created By	Created Date	Lookup Reference Column	Lookup On	Trans Lookup Condition	Last Modified By	Last Modified Date
Administrator	2020-01-12 20:40:27.5	ID		SELECT ID, SOURCE_OBJECT_ID, SOURCE_OBJECT_TYPE_ID, TARGET_OBJECT_ID, TARGET_OBJECT_TYPE_ID, RELATIONSHIP_DETAIL_ID FROM dbo.ADS_ASSOCIATION	Administrator	2020-01-12 20:40:27.5
Administrator	2020-01-12 20:40:27.5		ID		Administrator	2020-01-12 20:40:27.5
Administrator	2020-01-12 20:40:27.5				Administrator	2020-01-12 20:40:27.5

4. Click .

The lookup details are added in the Mapping Specification. You can add lookup details for multiple source columns.

Alternately, you can add transformation and lookup details to a mapping specification graphically. For more information about adding transformation and lookup details graphically, refer to the [Graphical Designer](#) topic.

Graphical Designer

You can add transformation and lookup details to a mapping specification on the Graphical Designer tab.

Adding transformation details involves setting up:

- Business rule
- Extended business rule transformation

Ensure that you define business rules under the Transformations node for the same ETL Option as the Project ETL. For more information on defining business rules, refer to the [Defining Transformations](#) section.

Adding lookup details involves setting up:

- Trans lookup condition
- Lookup reference column
- Lookup on

Ensure that you scan the required table in the Metadata Manager to set trans lookup condition.

Adding Transformation Details


To add business rules graphically, follow these steps:

1. Click the **Graphical Designer** tab.
2. Click .

You can now edit the mapping specification graphically.

3. Click the mapping link of the required column and expand the **Properties** pane.
4. Expand the **Transformation Details** pane.

Graphical Designer



5. Double-click the **Value** cell for **Business Rule** and select the required value.


6. Click .

The business rule is added to the mapping link. You can add business rules for multiple mapping links.

To add extended business rule transformations graphically, follow these steps:

1. On the **Graphical Designer** tab, Click .


The available options appear.



2. Select the **Extended Business Rule** check box.


Graphical Designer

3. Click the mapping link of the required column and expand the **Transformation Details** pane.



4. Double-click the **Value** cell for **Extended Business Rule Transformation**.


The Extended Transformation Rule Editor page appears.



5. Select the pseudocode based on the Project ETL.


For example, if the Project ETL is Informatica then select Informatica Pseudocode.


Graphical Designer



6. Press Ctrl + Space keys.

The available transformations appear.



If the required transformation is not available in the list, use  to create and update the transformations list.

7. Double-click the required transformation.

You can use to replace transformation name with pseudocode.


8. Click .

The extended business rule transformation is added to the mapping link. You can add extended business rule transformations to multiple mapping links.


Adding Lookup Details

To add lookup details graphically, follow these steps:

1. On the **Graphical Designer** tab, click the mapping link of the required column and expand the **Properties** pane.
2. Expand the **Lookup Details** pane.




3. Drag the required table from the **Metadata Tree View** pane and drop it for **Trans Lookup Condition**.



Graphical Designer

Once trans lookup condition is set, you can add lookup reference column and lookup on.

To add lookup reference column, double-click the cell for **Lookup Reference Column** and select the required option.



To add lookup on, double-click the cell against **Lookup On** and select the required option.

4. Click .

The lookup details are added to the mapping specification. You can add lookup details for multiple mapping links.


Updating Mapping Specifications Manually

After creating a mapping specification, you can update the mapping specification manually. However, we recommend that you use the manual method case by case on exception basis.

To update mapping specifications manually, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click a map.

By default, it opens the Mapping Specification tab.



The screenshot shows the 'Mapping Specification' tab in the software interface. On the left is a 'Workspace Mappings' tree view with a tree icon and a plus sign. The tree contains 'Mappings' (with a plus sign), 'Transformations' (with a plus sign), 'Projects' (with a plus sign), 'Carrefour (9)', 'Data Lake Migration (3)', 'EDW (3)', 'ERP (2)', 'Erwin_Project (4)', 'Erwin_Sales (1)', 'Transformations' (with a plus sign), 'Test Cases' (with a plus sign), 'Mappings' (with a plus sign), 'Integration' (with a plus sign), 'MappingTargets' (with a plus sign), 'Exeter (2)', and 'IQVIA (1)'. The 'Integration' folder is selected. The main area shows a grid with the following data:

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision	Target Colour Scale
1	Erwin_Sales_Target	Integration_Target	dbo.RM_RESOURC	RESOURCEID_New	int	4	10	0
2	Erwin_Sales_Target	Integration_Target	dbo.RM_RESOURC	RESOURCENAME_	varchar	100	0	0
3	Erwin_Sales_Target	Integration_Target	dbo.RM_RESOURC	RESOURCEDESC_	varchar	150	0	0

3. Click .

You can now edit the Mapping Specification grid.

4. Select a row (use Ctrl key to select multiple rows) and right-click the cell.

Updating Mapping Specifications Manually

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision	Target Column Scale
1	Erwin_Sales_Targe	Integration_Targe	dbo.RM_RESOURC	RESOURCEID_New	int	4	10	0
2	Erwin_Sales_Targe	Integration_Targe	dbo.RM_RESOURC	RESOURCENAME_	varchar	100		
3	Erwin_Sales_Targe	Integration_Targe	dbo.RM_RESOURC	RESOURCEDESC_N	varchar	150		

5. Use the following options:

Check All Rows

Use this option to select the check boxes under the Status column for the selected rows.



Right-click the header menu of the mapping specification grid and select the **Status** check box, to make Status column visible in the mapping specification grid.

Uncheck All Rows

Use this option to unselect the check boxes under the Status column for the selected rows.

Clear Source Details

Use this option to clear source details in the mapping specification grid.

Clear Target Details

Use this option to clear target details in the mapping specification grid.

Clear Source & Target Details

Use this option to clear source and target details in the mapping specification grid.

Updating Mapping Specifications Manually

Clear Cell

Use this option to clear the cell.

Delete Row(s)

Use this option to delete the selected rows.


Extended Properties

Use this option to configure Extended Properties.

Share Link

Use this option to copy or share the URL of the mapping specification.

To update cell values, double-click a cell and update its values.




#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision	Target Column Scale
1	Erwin_Sales_Targe	Integration_Targe	dbo.RM_RESOURCE	RESOURCEID_New	int	4	10	0
2	Erwin_Sales_Targe	Integration_Targe	dbo.RM_RESOURCE	RESOURCENAME	varchar	4		
3	Erwin_Sales_Targe	Integration_Targe	dbo.RM_RESOURCE	RESOURCEDESC_N	varchar			

Uploading Mapping Specifications in XML

You can upload a mapping specification to a project in the XML format. You can either use an existing XML file or export it from a suitable project. Ensure that the XML file follows the correct template. For more information on exporting a mapping specification in XML, refer to the [Proprietary XML Format](#) topic.

To upload mapping specifications in the XML format, follow these steps:


1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, right-click a project.




3. Click **Upload XML**.


The Upload Mapping Manager XML page appears.

Uploading Mapping Specifications in XML



4. Drag and drop or use  to browse and select the XML file.

The Upload Mapping Manager XML page appears.



Uploading Mapping Specifications in XML

5. Enter **Mail Comments** and click .

The Mapping Specification is uploaded successfully.

If you have enabled notifications, project users receive notification emails and mail comments from the administrator's email ID. For more information on configuring notifications, refer to the [Configuring Notifications](#) topic.


Specifying XPath in Mapping Specifications

Xpath is a potential path expression in XML documents. Hence, if you have imported source or target metadata from XSD files then it is important to specify Xpath. You can specify Xpath in a mapping specification for source and target columns.


To specify Xpath in mapping specifications, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click a map.

By default, it opens the Mapping Specification tab.





3. Right-click the header menu and select the **Target XPath** and **Source XPath** check boxes.




Specifying XPath in Mapping Specifications

The Target XPath and Source XPath columns are now visible in the Mapping Specification grid.

4. Click .
5. Double-click cells under the **Target XPath** and **Source XPath** columns to enter the required XPath.
6. Click .

The Xpath is specified in the Mapping Specification.



Target Column Data Type	Target XPath	Source Environment Name	Source Table Name	Source Column Name	Source XPath	Last Modified By	Last Date
string	./northwind/Empl School_Data	Order	ShipPostalCode	./northwind/Orde Administrator	21		
string	./northwind/Empl School_Data	Order	ShipName	./northwind/Orde Administrator	21		
string	./northwind/Empl School_Data	Order	ShipCountry	./northwind/Orde Administrator	21		
string	./northwind/Empl School_Data	Order	ShipCity	./northwind/Orde Administrator	21		
string	./northwind/Empl School_Data	Order	ShipAddress	./northwind/Orde Administrator	21		

Setting Column Order and Visibility


You can set the column order and visibility in Mapping Specifications and personalize the Mapping Specification grid. This helps you work efficiently.

Column Order

To set the column order in mapping specifications, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click a map.


By default, the Mapping Specification tab opens.



#	Source System Name	Source Environment Name	Source Table Name	Source Column Name	Source Column Data Type	Source Column Length	Business Rule
1	erwinDIS	erwinDIS	dbo.ADS_ASSOCI	ID	bigint	8	ABS
2	erwinDIS	erwinDIS	dbo.ADS_ASSOCI	SOURCE_OBJECT_	bigint	8	ABS
3	erwinDIS	erwinDIS	dbo.ADS_ASSOCI	SOURCE_OBJECT_	bigint	8	ABS

3. Click the required column header, drag and drop the column at the required place.

The Mapping Specifications can be exported with the new column order.

 Column ordering in Mapping Specifications are not saved and gets reset.


Column Visibility

To set the column visibility, follow these steps:


1. In the **Mapping Specification** grid, click .

The Header Menu page appears.

Setting Column Order and Visibility



2. Expand the respective nodes.
3. Select the required columns.



4. Close the **Header Menu** page.

The selected columns are visible in the Mapping Specification grid.

To reset column ordering and visibility click .

Updating Additional Mapping Information

You can update additional mapping information in the Additional Mapping Information pane with respect to the following tabs:

Tab	Description
Map Spec Overview	Under this, you can update the following for a mapping specification: <ul style="list-style-type: none"> ▪ Specification name ▪ Version label ▪ State name and sub-state name ▪ Source and target metadata sync ▪ Job Name XRef
Source Extract SQL	Under this, you can update: <ul style="list-style-type: none"> ▪ SQL Query relevant to a mapping specification ▪ SQL Query Description
Target Update Strategy	Under this, you can set your target update strategy as per your data integration requirements.
Testing Notes	Under this, you can add relevant testing notes with respect to a mapping specification.
Map Specs Docs	Under this, you can upload relevant documents.
Assignment	Under this, you can assign a mapping specification to multiple users.
Specification Artifacts	Under this, you can link additional specification artifacts relevant to a mapping specification.
Level of Effort	Under this, you can record planned level of effort and actual level of effort in creating mapping and ETL process.
Change Log	This tab can be enabled in Mapping Manager Settings . Under this, you can capture change logs of a mapping specification.
Release Information	Under this, you can view release information of a mapping.
My Action	Under this, you can collaborate with other users on a task.

Updating Additional Mapping Information

Tab	Description
Center	
User Defined Tabs (1-5)	There are five user defined tabs that can be used by you with your own UI labels .
Extended Properties	Under this, you can extend properties of a mapping specification by creating custom forms.

To access the Additional Mapping Information pane, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click a map.

The central pane displays the Mapping Specification grid. The Additional Mapping Information pane is available at the bottom of the central pane.

The screenshot shows a software interface with a 'Mapping Specification' grid at the top and an 'Additional Mapping Information' pane at the bottom. The grid has columns for #, Target System Name, Target Environment Name, Target Table Name, Target Column Name, Target Column Data Type, Target Column Length, Target Column Precision, Target Column Scale, and Target Column Name. It contains four rows of data for a table named 'dbo.Categories'.

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision	Target Column Scale	Target Column Name
1	SQLTechPubs	SQLTechPubs	dbo.Categories	CategoryID	int	4	10	0	CategoryID
2	SQLTechPubs	SQLTechPubs	dbo.Categories	CategoryName	nvarchar	15	0	0	CategoryName
3	SQLTechPubs	SQLTechPubs	dbo.Categories	Description	ntext	16	0	0	Description
4	SQLTechPubs	SQLTechPubs	dbo.Categories	Picture	image	16	0	0	Picture

Below the grid, there is a pagination bar showing 'Records from 1 to 4', 'Page 1', and '100 rows per page'. The 'Additional Mapping Information' pane is expanded, showing tabs for 'Map Spec Overview', 'Source Extract SQL', 'Target Update Strategy', 'Testing Notes', and 'Map Spec Docs'. The 'Map Spec Overview' tab is currently selected.

3. Click the **Additional Mapping Information** pane.

You can use or to navigate across the pane.

Updating Additional Mapping Information

The screenshot displays the 'Mapping Specification' window in the 'Graphical Designer' tab. The main area shows a table with columns for mapping details. Below the table is a navigation bar with 'Records from 1 to 4', 'Page 1', and '100 rows per page'. The 'Additional Mapping Information' section is expanded, showing a 'Map Spec Overview' tab. This section contains various fields for map configuration, including Map Id, Specification Name, Map Specification Version, Version Label, State Name, Sub State Name, and metadata sync options.

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision	Target Column Scale	Target Column Nu
---	--------------------	-------------------------	-------------------	--------------------	-------------------------	----------------------	-------------------------	---------------------	------------------

Records from 1 to 4 | Page 1 | 100 rows per page

Additional Mapping Information

Map Spec Overview | Source Extract SQL | Target Update Strategy | Testing Notes | Map Spec Docs

Map Id: 98 | Workflow Status: Preliminary Draft

Specification Name: BugTrial

Map Specification Version: 1.00

Version Label:

State Name: Approved | Sub State Name:

Sync Source Metadata: OFF | Sync Target Metadata: OFF

Job Name XRef:

Updating Map Spec Overview

You can update the Map Spec Overview tab and update various aspects of a mapping specification that includes:

- Specification name and its description
- Version label
- Mapping states and sub-states
- Syncing metadata with a mapping specification
- Job name XRef

To update the Map Spec Overview tab, follow these steps:

1. In the **Additional Mapping Information** pane, on the **Map Spec Overview** tab, click .

Updating Map Spec Overview

Additional Mapping Information

Map Spec Overview
Source Extract SQL
Target Update Strategy
Testing Notes

Map Id

Specification Name Bug Trial

Map Specification Version

Version Label

State Name Approved ▼ Sub State Name Select ▼

Sync Source Metadata

Job Name XRef

Mapping Description

A H B I U

Testing for a bug logged by QA

Workflow Status Preliminary Draft

Assigned To

Created By Administrator Created Date Time 2020-06-08 10:24:06.843

Modified By Administrator Modified Date Time 2021-04-22 08:11:29.353

- Select or enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Specification Name	Specifies the mapping specification name. For example, EDW_PROD_IDS_Benefits_Detail. For more information on naming conventions, refer to the Best Practices section.
Version Label	Specifies the version label of the mapping specification. For example, EDW_PROD_IDS_Benefits_Detail (Alpha). For more information on configuring version display of maps, refer to the Configuring Version Display topic.
State Name	Specifies the mapping state of the mapping specification.

Updating Map Spec Overview

Field Name	Description
	For example, In Progress. For more information on configuring mapping states, refer to the Configuring Mapping State Settings topic.
Sub State Name	Specifies the sub-state of the mapping specification. For example, Needs Approval. For more information on configuring mapping sub-states, refer to the Configuring Mapping State Settings topic.
Sync Source Metadata	Switch Sync Source Metadata to ON to sync source metadata with the mapping specification.
Sync Target Metadata	Switch Sync Target Metadata to ON to sync target metadata with the mapping specification.
Job Name XRef	Specifies the equivalent ETL mapping name. For example, ErwinDIS931.
Description	Specifies the description for the mapping specification. For example: This is a map between EDW source and IDS target systems.



You cannot edit Map Id, Workflow Status, and Map Specification Version.

For more information on workflow status, refer to the [Managing Mapping Manager Workflows](#) topic.

3. Click .

The fields on the Map Spec Overview tab are updated.


Updating Source Extract SQL

You can keep a record of multiple source extract SQL and its description. You can also update it as per your requirements.

To update source extract SQL, follow these steps:


1. In the **Additional Mapping Information** pane, click the **Source Extract SQL** tab.

The Source Extract SQL tab appears.



2. click .

Updating Source Extract SQL



3. Enter **SQL Query** and **SQL Query Description**.

For example:

- **SQL Query:** Select * from dbo.RM_Resource
- **SQL Query Description:** - The query extracts the data from dbo.RM_Resource table.

4. Click .


The Source Extract SQL is updated.

Setting Target Update Strategy


You can set the way target metadata is updated when you map source to target. You can update the strategy any time as per your requirement.

To set target update strategy, follow these steps:

1. In the **Additional Mapping Information** pane, click the **Target Update Strategy** tab.




2. Click .



3. Click the appropriate update strategy from the options and enter **Update Strategy Description**.

For example:

Setting Target Update Strategy

- **Update strategy:** Insert else Update
 - **Update Strategy Description:** Insert the source column value to a blank target column else update the target column value with the source column value.
4. Click .

The Target Update Strategy is set.


Updating Testing Notes

You can keep a record of testing notes related to a mapping specification and specify test results as:


- Un-specified
- Pass
- Fail
- Needs analysis

To update testing notes, follow these steps:

1. In the **Additional Mapping Information** pane, click the **Testing Notes** tab.



2. Click .



Updating Testing Notes

3. Click the appropriate option for test results and enter **Testing Notes**.

For example:

- **Test results:** Pass
- **Testing Notes:** The mapping specification passed the testing and it is ready for the ETL process.

4. Click .


The Testing Notes are updated.

Adding Mapping Specification Documents


You can add supporting documents, such as text files, audio files, video files, document links, and so on to a mapping specification.

To upload mapping specification documents, follow these steps:

1. In the **Additional Mapping Information** pane, click the **Map Spec Docs** tab.




2. Click .



3. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Adding Mapping Specification Documents

Field Name	Description
Document Name	Specifies the name of the physical document being attached to the mapping specification. For example, Mapping Details.
Document Object	Drag and drop document files or use  to select and upload document files.
Document Owner	Specifies the document owner's name. For example, John Doe.
Document Link	Specifies the URL of the document. For example, https://drive.google.com/file/d/2sC2_SZlYeFKI70On-b5YkMBq4ptA7jhg5/view
Description	Specifies the description of the document. For example: The document has information about the mapping details.
Approval Required Flag	Specifies whether the document requires approval. Select the Approval Required Flag check box to select the document status.
Document Status	Specifies the status of the document. For example, In Progress. Select the status of the document from the drop down. This field is available only when the Approval Required Flag check box is selected.

4. Click .

The mapping specification document is added.

Assigning Mapping Specifications to Users

You can assign a mapping specification to your team members in the following capacities:

- Mapping Designer
- Mapping Approver
- Mapping ETL Developer
- Mapping Tester

By default, the user that creates the mapping specification is the Mapping Designer. You can re-assign another user as the Mapping Designer.

To assign mapping specifications to users, follow these steps:

1. In the **Additional Mapping Information** pane, click the **Assignment** tab.

	Assigned To	Status
Mapping Designer	Administrator - Default System User(Admin)	In Progress
Mapping Approver	Jane Doe(janedoe)	Not Started
Mapping ETL Developer	Joey Wilson(jwilson)	Not Started
Mapping Tester	public - Default System User(public)	Not Started

Distribution / CC List

Custom Notes

2. Click .

Assigning Mapping Specifications to Users

Additional Mapping Information

Target Update Strategy Testing Notes Map Spec Docs **Assignment** Specification Artifacts

Assigned To

Mapping Designer: Administrator - Default System User(Administ...)

Mapping Approver: Jane Doe(janedoe)

Mapping ETL Developer: Joey Wilson(jwilson)

Mapping Tester: public - Default System User(public)

Distribution / CC List

Status

Mapping Designer: In Progress

Mapping Approver: Not Started

Mapping ETL Developer: Not Started

Mapping Tester: Not Started

Email

Custom Notes

Rich text editor toolbar: Bold, Italic, Underline, List, etc.

Assignment changes

Rich text editor toolbar: Bold, Italic, Underline, List, etc.

3. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Mapping Designer	Specifies the User Full Name and User ID of the Mapping Designer. For example, Jane Doe(janedoe).
Mapping Approver	Specifies the User Full Name and User ID of the Mapping Approver. For example, John Doe(jdoe).
Mapping ETL Developer	Specifies the User Full Name and User ID of the Mapping ETL Developer. For example, John Denver(jdenver).
Mapping Tester	Specifies the User Full Name and User ID of the Mapping Tester. For example, Michael Samuel(M.Samuel).
Status	Specifies the status of the user's task. For example, Pending Review.
Email	The Email check boxes populate as you select corresponding users.

Assigning Mapping Specifications to Users

Field Name	Description
	Select the check boxes to send email notifications to the corresponding users about the mapping assignment and change in mapping status. For more information on configuring email notifications, refer to the Configuring Notifications topic.
Distribution/CC List	Enter a comma-separated list of email IDs that should receive the email notification about the assignment. For example, ab.dav@xyz.com, cal.kai@xyz.com The email notification is sent from the administrator's email ID .
Custom Notes	Specifies custom notes about the mapping assignment. For example: John Denver is the Mapping ETL Developer of the mapping specification.
Assignment Changes	Specifies the changes in the mapping assignment. The information in this field is system-generated. For example: User Administrator - Default System User(Administrator) has been assigned to the mapping on 2020-01-12 19:58:15.815.

4. Click .


The mapping specification is assigned to the users.

Linking Additional Specification Artifacts


The Requirements Manager captures functional requirements of a data integration project using Specification Artifacts. You can link these specification artifacts with mapping specifications.

To link specification artifacts with mapping specifications, follow these steps:

1. In the **Additional Information** pane, click the **Specification Artifacts** tab.




2. Click .



Linking Additional Specification Artifacts

3. In the right pane, expand the **Specification Artifact Catalog** pane and drag and drop the required specification under the **Specification Artifacts** tab.



4. Click .


The specification artifact is linked.

Recording Level of Effort


You can record and compare planned level of effort with the actual level effort spent on creating and managing mapping specifications.

To record the level of effort, follow these steps:

1. In the **Additional Mapping Information** pane, click the **Level of Effort** tab.



2. Click .



3. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Sub-Fields	Description
Planned Level of Effort	Mapping Effort	Specifies the planned mapping effort in days. For example, 12.1 days.
	ETL Effort	Specifies the planned ETL effort in days.

Recording Level of Effort

Field Name	Sub-Fields	Description
		For example, 10.5 days.
	Notes	Specifies notes about the planned level of effort. For example: Planned level of effort took all the project requirements into account.
Actual Level of Effort	Mapping Effort	Specifies the actual mapping effort in days. For example, 12.1 days.
	ETL Effort	Enter the actual ETL effort in days. For example, 9.5 days.
	Notes	Specifies the notes about the actual level. For example: Actual level of effort were lesser than the planned level of effort.

4. Click .

The level of effort tab is recorded.

Viewing Change Logs

A change log is a record of changes made in a Mapping Specification grid. You can view these changes on the Change Log tab. By default, this tab is disabled. You can enable it under Change Log Settings. For more information, refer to the [Configuring Change Log Settings](#) topic.

To view the change logs of the mapping specifications, in the **Additional Information** pane, click the **Change Log** tab.

The change logs of the mapping specification appears.

The screenshot shows the 'Mapping Specification' window with the 'Change Log' tab selected in the 'Additional Mapping Information' pane. The main window displays a table of target columns for a mapping specification named '[BugTrial]'. The 'Additional Mapping Information' pane shows a table of change logs for this mapping specification.

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision	Target Column Scale	Target Column Nullable
1	SQLTechPubs	SQLTechPubs	dbo.Categories	CategoryID	int	4	10	0	

#	Log Id	Changed Log Description	Map Version	Last Modified By	Last Modified Date Time
1	58		1.00	Administrator	2020-08-27 14:13:23.08
2	43	Trial for bug testing	1.00	Administrator	2020-06-08 10:28:46.793
3	42	Testing the flow for a bug.	1.00	Administrator	2020-06-08 10:26:50.783

Viewing Release Information

The release, migration, and audit-related information of a mapping specification are available on the Release Information tab. For more information on releases, refer to the [Release Manager](#) section.

To view release information of mapping specifications, in the **Additional Mapping Information** pane, click the **Release Information** tab.

The release information of the mapping specification appears.

Additional Mapping Information					
Spec Docs	Assignment	Specification Artifacts	Level of Effort	Change Log	Release Information
Release Details					
Release	DeltaRelease		Project	ErwinSales	
Status	PENDING APPROVAL		Owner	Administrator	
Migration Details					
From	DEV		To	DEV	
Live Date	06/18/2021 HH:MM AM/PM		Migration Date	06/18/2021 HH:MM AM/PM	
Audit Details					
Created By	Administrator		Created Date	06/18/2021	
Last Modified By	Administrator		Last Modified Date	06/18/2021	


Adding Tasks

To collaborate on mappings you can create tasks depending on your requirement. By default, you can create to-do tasks, access requests, or issues. Apart from these task types, you can configure custom task types via Task Type Configuration.

To add tasks, follow these steps:

1. In the **Additional Mapping Information** pane, click the **My Action Center** tab.


The My Action Center tab opens. It displays a list of all tasks related to the map.



2. Click .

A list of task types appears.

Adding Tasks




3. Click the required task type.

The Create New Task page appears.


A screenshot of the "Create New Task" form. The form is titled "Create New Task" and has a "TASK DETAILS" section. It shows that the task is being created on an asset named "Data Integration MAPPING". The task type is set to "To-do Task". The name field contains "MAPPING_Data Integration_" with a character count of 25 / 200. The description field is empty with a character count of 0 / 5. There is a "Self Help" button on the right side of the form. The "Important" field has two radio buttons, "YES" and "NO", with "NO" selected. The "Due" field is empty. The "Assign Users" field contains "Richard Cooper" with a character count of 0 / 5. There is a "Hit the ENTER key to add a new Email" instruction at the bottom.

Adding Tasks

4. Enter appropriate values in the fields. Refer to the following table for field descriptions.

Field Name	Description
Task is being created on Asset	Specifies the asset for which the task is created. This field autopopulates with the map name.
With Task Type as	Specifies the task type. For example, To do Task.
Name	Specifies the name of the task. By default, it autopopulates with a name in the following format: Mapping_<Map_Name>. You can edit it and rename the task. For example, Test Mappings.
Description	Specifies a description of a task. For example: Test all the mappings and record the effort required.
Important	Specifies whether the task is important
Due	Specifies the due date of the task. Use  to set the due date.
Assign Users	Specifies the users assigned to the task. You can assign DI and BU users from the list. For example, Richard Cooper.
External user emails	Specifies the email ID of external users. For example, chris.harris@quest.com

5. Click .

The task is created and saved. Use  to edit the task details and attach relevant documents.

Chat

Use the Chat tab to send messages to the assigned and external users of a task.

Adding Tasks

On the **Chat** tab, enter your message in the text box and use the following options:


Assigned

Use this option to send messages to the assigned users.

External Users

Use this option to send messages to external users.

Users are notified via Messaging Center.



You can manage a task using the options available on the task list. [Managing a task](#) involves:

- Marking tasks complete
- Viewing task details
- Editing task details
- Disabling notifications
- Downloading Chat
- Sharing chat
- Marking tasks as pending
- Deleting tasks

With the My Action Center tab, you can filter and search tasks based on its status and assignments. For more information on search and filter mechanisms, refer to the [Filter and Search](#) topic.


Configuring Task Types

With My Action Center, you can configure task types to collaborate on miscellaneous tasks. By default, three task types, To-Do Task, Request Access, and Issue are available. These task types cannot be edited or deleted.

To configure task types, follow these steps:

1. On the **My Action Center** tab, click .

The Task Type Configuration page appears. It displays a list of available task types.




2. Enter a new task type in the space provided, and then click .

The task type is added in the list of available tasks.

For example, in the following image, a task type, schedule job is added in the Task Types list.

Configuring Task Types



3. Use the following options to manage task types:

Edit ()

Use this option to edit the task type.

Delete ()

Use this option to delete a task type.

Managing Tasks


Managing tasks involves:

- Marking tasks complete
- Viewing task details
- Editing task details
- Disabling notifications
- Downloading Chat
- Sharing chat
- Marking tasks as pending
- Deleting tasks

To mark tasks complete, on the task list, for the required task, click the radio button.

The task is moved to the list of completed task.

For example, in the following image, the task, Add Business rule is marked complete.




To manage tasks, follow these steps:

1. In the task list, for the required task, click ⋮.

The available options appear.

Managing Tasks



2. Use the following options to work on tasks:

View Task Details

Use this option to view task details. These details include task name, description, assigned assets, attached documents, and so on.

Edit Task Details

Use this option to update task details.

Disable Notification

Use this option to stop receiving notifications related to a task. By default, notifications are enabled, and users assigned to task receive notifications.

Download Chat as Text


Use this option to download chat related to a task in the TXT format.


Send Chat as Email

Use this option to share the chat related to a task via an email. Click **Send Chat as Email**.

The Email Selection page appears. It displays a list of users assigned to the task.

Managing Tasks



Select the required users, and then click . An email is sent to the selected users.

Mark as Pending

This option is available for a completed task. Use this option to mark a task as pending.

To delete a task, in the task list, for the required task, click .



You can delete a task only if you have created the task.


Configuring Extended Properties

You can configure user-defined properties of a mapping specification under the **Extended Properties** tab.


First, you need to set up a form and then use it to configure the user-defined extended properties.

To configure extended properties of mapping specifications, follow these steps:

1. In the **Additional Mapping Information** pane, click the **Extended Properties** tab.




2. Click **Configure**.



Configuring Extended Properties

The **Extended Properties Configuration** page contains the following sections:

- **Field Controls:** Use this pane to get the required UI elements.
 - **Configure Form:** Use this pane to design forms using the UI elements available in the **Field Controls** pane.
 - **Properties:** Use this pane to view the properties of the UI element selected in the **Configure Form** pane.
3. Click **Edit**. Then, double-click or drag and drop the required UI elements from the **Field Controls** pane to the **Configure Form** pane.
 4. Select UI elements, one at a time, and configure their properties in the **Properties** pane.



Property	Value
Published	ON
Field	Rich Editor
Type	Rich Editor
Dependencies	Type or click here
Configure Values	Configure
Mandatory	OFF
Regular Expression	

Note: 1. Double click on the field cell to update the field name
2. Select the field name to update its properties



The available properties differ based on the type of UI element.

Refer to the following table for property descriptions:

Property	Description
Published	Switch Published to ON to publish the field.
Field	Specifies the field label.

Configuring Extended Properties

Property	Description
	To change the field labels, double-click the corresponding Value cell. For example, Mapping Specification Approved On.
Type	Specifies the type of the field. To select field types, double-click the corresponding Value cell. For example, Date Picker.
Dependencies	Defines the pick list fields that can be used as controlling fields. It works only with the Reference Data Manager connector. To define pick list fields, select the fields from the drop down option.
Configure Values	Specifies the connectors for the field. To enter option values, click Configure Values . Use the following options: <ul style="list-style-type: none"> ▪ Default connector: Use this option to enter option values manually or using an MS Excel file. ▪ Reference Data Manager: Use this option to pull option values from reference tables in the Reference Data Manager.
Mandatory	Specifies whether the field is mandatory.
Description	Specifies the field description. To enter field descriptions, double-click the corresponding Value cell.
Visible in Extended Properties	Switch Visible in Extended Properties to ON to make it visible on the Extended Properties tab.
Order	Specifies the order of the field on the Extended Properties tab. To enter the order number, double-click the corresponding Value cell. You can also drag and move fields in the Configure Form pane to change its order.

5. Click **Save**.

Configuring Extended Properties

The form is saved and is available on the **Extended Properties** tab.

You can download extended properties in the XLSX format and use it as a template to [import extended properties](#). To download extended properties, on the **Extended Properties** tab, click **Export To Excel**.

Default Connector

When you configure extended properties using UI elements, such as combo box, radio button, and list, you also need to configure their option values. You can use the default connector to import option values from an MS Excel file or enter them manually.


To configure option values using the default connector, follow these steps:

1. In the **Configure Form** section, click the required UI element.

Ensure that you are in edit mode.

2. In the **Properties** section, click **Configure**.


The Connectors page appears.



3. On the **Connectors** page, ensure that the Default Connector option is selected. Then, click **Next**.

The <UI_Element> Options page appears. For example, if the UI element is Combo Box, the Combo Box Options page appears.

Default Connector



4. Use the following options:

Add

Use this option to enter text and value manually.

Import Excel

Use this option to import options from MS Excel files.

5. After configuring option values, click **Save**.

To add option values manually, follow these steps:

1. Click **Add**.
2. Enter values to the Text and Value fields.

The Text corresponds to options whereas the Value corresponds to underlying value of an option. You can add as many values as needed.

Default Connector

Text	Value
<input type="text"/>	<input type="text"/>
Data Steward_GER	rcooper
Data Steward_ROM	vsmith
<input type="text"/>	<input type="text"/>

3. Click **Save**.

The option values appear in the UI element under the Configure Form section.


Combo Box Select an option ▼
Select an option
Data Steward_GER
Data Steward_ROM

To import option values from MS Excel files, follow these steps:

1. Click **Import Excel**.

The Upload Excel page appears.

Default Connector



2. Click **Choose File** and select the required MS Excel file.

The Upload Excel page appears. It displays the data in the MS Excel file.

#	GROUP NAME	ROLE NAME	USER ID
#	Select Column To Import	Select Column To Import	Select Column To Import
1	Data Stewards	Data Steward_GER	mmannigan
2	Data Stewards	Data Steward_GER	mmenza
3	Data Stewards	Data Steward_GER	mmannigan

3. Double-click the **Select Column To Import** cell in the required column.

The available options appear.

#	GROUP NAME	ROLE NAME	USER ID
#	Select Column To Import	Select Column To Import	Select Column To Import
1	Data Stewards	Data Steward_GER	mmannigan

Dropdown menu options:

- Select Column To Import
- FIELD
- VALUE
- Clear Selection


Default Connector

4. Select the appropriate option.

Field corresponds to options and Value corresponds to value of an option. You can import multiple columns. Use Clear Selection to undo the selection.

5. Click .


The <UI_Element> Options page appears. It displays the imported columns. You can delete a row that is not required. To delete rows, click a row and then click **Delete**.



Text	Value
Data Steward_GER	mmanigan
Data Steward_UK	rcooper
Data Owner_GER	esimpson
Data Owner_RO	ksridhar
Tech Data Steward_GER	jadams

6. Click **Save**.

The option values appear in the UI element under the Configure Form section.



Combo Box Select an option ▼

List

- Select an option
- Data Steward_GER**
- Data Steward_UK
- Data Owner_GER
- Data Owner_RO
- Tech Data Steward_GER
- Mapping Admin
- ETL Developer
- Mapping Designer

Reference Data Manager

When you configure extended properties using UI elements, such as combo box, radio button, and list, you also need to configure their option values. You can use the Reference Data Manager connector to import option values from tables in the Reference Data Manager.

To configure option values using reference data manager connector, follow these steps:

1. In the **Configure Form** section, click the required UI element.

Ensure that you are in edit mode.


2. In the **Properties** section, click **Configure**.

The Connectors page appears.




3. On the **Connectors** page, click **Reference Data Manager** and then click **Next**.

The Reference Data Manager page appears. It displays the reference folders in the Connector View pane.



4. In the **Connector View** pane, expand a reference folder and select a reference table. The Parameters pane displays the columns in the reference table. You can also click Preview to view the data in the reference table.

Reference Data Manager



5. In the **Parameters** pane, click the radio button next to the required column.
You can select the controlling field from the drop down option. Ensure that you define the required dependencies in the Properties pane and that the option values for controlling field are configured using the same reference column.
6. Click **Finish**.
The Extended Properties Configuration page appears.

Reference Data Manager

Extended Properties Configuration

Save Cancel Delete

Field Controls

Group Text Box Combo Box List Radio Check Box Number Boolean Date Picker Category

Configure Form

Selected Roles Group Compliance Officer

List of Cities

Mumbai
Los Angeles
New Delhi

Radio

Properties

Property	Value
Description	
Load On Startup	OFF
Visible in Extended Properties	ON

7. Under the **Properties** section, switch **Load on Startup** to **ON**.
8. Click **Save**.

The option values are configured. For example, in the following form the List of Cities is the controlling field for Selected City. Both the fields get their option values from the same reference column.

Configure Form

Governance Responsibilities Compliance Officer

Selected Roles Group Compliance Officer

List of Cities

Mumbai
Los Angeles
New Delhi

Selected City Los Angeles


Importing from Excel


You can import user-defined properties of a mapping specification from an XLSX file. You can either use an existing XLSX file or download a extended properties file from a mapping specification. Ensure that the XLSX file follows the correct template.

To import extended properties from XLSX files, follow these steps:

1. On the **Extended Properties** tab, click **Import From Excel**.

The Upload Excel page appears.



2. Click **Choose File**.
3. Browse and select the XLSX file.
4. Click .

The Upload Excel page appears. It displays the data in the XLSX file.

#	FIELD	VALUE	TYPE	PARENTFIELD	CREATED_BY	CREATED_DATE_TIME
#	Select Column To Import	Select Column To Import	Select Column To Import	Select Column To Import	Select Column To Import	Select Column To Import
1	Data Stewards		Combo Box			
2	Data Steward_UK	Data Steward_UK	Text Box	/Data Stewards	Administrator	10/20/2020 06:42:38
3	Data Steward_GER	Data Steward_GER	Text Box	/Data Stewards		
4	Data Owners	Data Owner_GER	Text Box		Administrator	10/20/2020 06:42:38

5. Double-click the **Select Column To Import** cell in the required column.

The available options appear.

Importing from Excel

#	FIELD	VALUE	TYPE	PARENTFIELD
#	Select Column To Import	Select Column To Import	Select Column To Import	Select Column To Import
1			Combo Box	
2	Data Steward_UK	Data Steward_UK	Text Box	/Data Stewards
3	Data Steward_GER	Data Steward_GER	Text Box	/Data Stewards

6. Select an appropriate option.

For example, if you select Field, then the selected column is imported as Field.

Similarly, you can also select the Value, Type, and Parentfield columns. Ensure that you at least select a Field column.

7. Click .

The extended properties are imported.

Buttons: Configure, Edit, Delete, Import From Excel, Export To Excel

Form Values

Data Stewards Select an option

Data Owners Data Owner_GER

Technical Data Steward Tech Data Steward_GER

Compliance Officer Mapping Designer

Self Help

Branching and Merging Maps

Branching a map enables multiple users to work on a mapping specification. You can create multiple branches of a parent map depending on the number of users. Different users can work on these branches and make changes in the mapping specification. These branches can then be merged into the parent map.

Branching and merging maps involves:


- [Branching maps](#)
- [Merging changes into parent maps](#)

Branching Maps

Branching a map means copying the map and pasting it in another subject area or a project. The copied map acts as a child map and the original map is called the parent map.


To branch maps, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, right-click a map and hover over the **Copy Map**.




3. Click **Copy Selected**.
4. Right-click the **Mappings** node under the required project or subject area.

Branching Maps



5. Click **Paste**.

The mail comments page appears.



6. Enter **Mail Comments** and click .

The map is copied successfully into the subject area or the project. You can rename the child map and modify as needed. For example, you can change the reference

Branching Maps

table, business rule, or add or remove columns. For more information on renaming mappings, refer to the [Updating Map Spec Overview](#) topic.


If you enable notifications in Mapping Manager Settings, project users receive an email notification when the map is copied to a project. For more information on configuring notifications, refer to the [Configuring Notifications](#) topic.

Merging Changes into Parent Maps

After making the required changes in a child map you can merge it with a parent map. You can also notify project users about the merge through email notifications.

To merge child maps with parent maps, follow these steps:


1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, right-click a parent map.



3. Click **Merge Mapping**.

The Merge Map page appears.


Merging Changes into Parent Maps



4. Select a child map.

5. Click .

The Merge Map page shows the changed data with respect to the parent map.



Merging Changes into Parent Maps

6. Use the following options:

Overwrite existing version

Use this option to overwrite the existing version.

Create New Version

Use this option to create new version of the parent map.

7. Enter relevant **Mail Comments**.

8. Click .

The child map is merged with the parent map.

If you enable notifications in the Mapping Manager Settings the project users receive mail comments through an email notification. For more information on configuring notifications, refer to the [Configuring Notifications](#) topic.

Deleting Maps


You can delete maps that are not required in a project. You can also opt to delete all the versions of a map.

To delete maps, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, select a map or multiple maps.

You can use shift key to select multiple maps.


3. Right-click the selection.



4. Click **Delete Mapping(s)**.

The Delete Mappings-Selected Mappings List page appears.

Deleting Maps



#	Project Hierarchy	Map Name	Current Version	All Versions	
			<input type="radio"/>	<input type="radio"/>	
1	Sales Data Mart	4_L_Customer_dim	<input type="radio"/>	<input type="radio"/>	✘
2	Sales Data Mart	3-L_Customer	<input type="radio"/>	<input type="radio"/>	✘

5. Use the following options:

Remove Mapping from Current Selection (✘)

Use this option to remove mappings from the current selection.

Delete all Versions

Use this option to delete all versions of the mappings.

Delete Current Version

Use this option to delete current version of the maps.

Viewing Workflow Logs


A default workflow, Mapping_Manager_Default_Workflow is assigned to all projects in the Mapping Manager. You can also create a workflow and assign it to your project. For more information on assigning workflow to projects, refer to the [Managing Mapping Manager Workflows](#) section.

You can view the flow of actions of the workflow assigned to a map. Along with other information, the workflow displays the current state of the map in the workflow.

To view workflow logs, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click a map.

By default, the Mapping Specification tab opens.




#	Source System Name	Source Environment Name	Source Table Name	Source Column Name	Source Column Data Type	Source Column Length	Business Rule
1	erwinDIS	erwinDIS	dbo.ADS_ASSOCI	ID	bigint	8	ABS
2	erwinDIS	erwinDIS	dbo.ADS_ASSOCI	SOURCE_OBJECT_	bigint	8	ABS

3. Click the **Workflow Log** tab.

The workflow log of the map appears. The current workflow stage blinks in the diagram.

Viewing Workflow Logs



Use the following options:

User Comments (👤)

Use this option to view users and their comments in each stage.

Expand/Hide Users and Roles

Use this option to view or hide users and roles assigned to workflow stages.

Collapse/Expand Roles

Use this option to switch between the collapsed and expanded roles view. This option is enabled when you are in the Expand Users and Roles view.

Collapse/Expand Users

Use this option to switch between the collapsed and expanded users view. This option is enabled when you are in the Expand Users and Roles view.

Export Image

Use this option to download the workflow in the JPG format.

Analyzing Mappings

This section walks you through the multiple ways of analyzing source to target mappings.

Analyzing mappings involves:

- Data preview
 - [Generating virtual preview of target](#)
 - [Previewing data through Metadata Tree View](#)
- Gap analysis
 - [Performing table gap analysis](#)
 - [Performing column gap analysis](#)
- Impact analysis
 - [Running impact analysis for tables and columns](#)
- Lineage analysis
 - [Running dual, forward, or reverse lineage analysis](#)
 - [Running end to end lineage](#)
- [Business view](#)
- [Mapping statistics](#)

Generating Virtual Preview of Targets

When you create a mapping specification, source column values undergo modifications based on the applied transformations. These modified values are updated in target columns based on the target update strategy. You can generate a virtual preview of targets to view the updated target columns.



Mapping specifications involving multiple source or target systems do not support virtual preview of targets.

To generate a virtual preview of targets, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click a map.

The Mapping Specification grid appears.

#	Source System Name	Source Environment Name	Source Table Name	Source Column Name	Source Column Data Type	Source Column Length	Business Rule
1	Erwin_Sales	Integration	dbo.RM_RESOURCE	RESOURCEID	int	4	FLOOR
2	Erwin_Sales	Integration	dbo.RM_RESOURCE	RESOURCENAME	varchar	100	REVERSE
3	Erwin_Sales	Integration	dbo.RM_RESOURCE	RESOURCEDESC	varchar	150	

3. Click


Mapping Preview page appears, displaying the virtual preview of the target based on the source and transformations.

Generating Virtual Preview of Targets




Mapping preview is currently supported for RDBMS only. Here is the list of transformation supported in Mapping Preview:

CONCAT, LTRIM, RTRIM, TRIM, CEIL, FLOOR, RPAD, LPAD, ROUND, SQRT, SUBSTR, UPPER, LOWER, TRUNC, SIN, COS, TAN, SINH, TANH, REVERSE, IS_DATE, IS_NUMBER, IS_SPACES, ISNULL, IIF, ISEMPTY, NVL, DECODE.



RESOURCEID_New	RESOURCENAME_New	RESOURCEDESC_New	RESOURCECELLPHONE_New	RESOURCEHOMEPHONE_New	RESOURCEEMAIL_New
1	nimdA				
2	rahdiS kItaK				
3	emaN_ecluoseR	desc			
4	steliV eoJ				

You can download the mapping preview details in the XLSX format. To download the mapping preview details, click  .

Previewing Data

You can preview data in a table using the Metadata Tree View pane. You can also enter SQL queries to preview the required data in the database.

To preview data from databases, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click a project.

The Metadata Tree View pane appears on the right.

The screenshot shows the Mapping Manager interface. On the left is the 'Workspace Mappings' pane with a tree view containing 'Mappings', 'Data Integration (v1.00)', 'DragDrop (v1.00)', 'SalesforceIntegration (v1.00)', and 'TechPubs (v1.00)'. The 'project 1 (4)' item is selected. On the right is the 'Mapping Summary' table with the following data:

#	Project Name	Subject Hierarchy	Map Name	Lock Status	Locked By	Locked Date	Workflow Status	Mapping State
1	project 1		Account_Tableau_f				Preliminary Draft	In Progress
2	project 1		T		Administr	23-05-2020 18:55:40	Preliminary Draft	In Progress

3. In the **Metadata Tree View** pane, right-click a table and hover over **Preview Data**.


Previewing Data

Click this option to preview the first 1000 records.

Advanced Preview


Click this option to preview data based on a SQL query.

For example, if you click **Preview 100 Records**, then the User Credentials page appears.




5. Enter **User Name** and **Password** to connect with the database.

You can preview the data based on the options you selected.



#	CAT_DIALOG_TAB_ID	CAT_DIALOG_PROFILE_ID	CAT_DIALOG_TAB_NAME	CAT_DIALOG_TAB_PROPERTIES	CREATED_BY	CREATED_DATE_TIME
1	1	1	DefaultTab		Administrator	2018-09-14 10:39:46.02
2	2	2	DefaultTab		Administrator	2018-09-14 10:39:46.02
3	3	3	DefaultTab		Administrator	2018-09-14 10:39:46.02
4	4	4	DefaultTab		Administrator	2018-09-14 10:39:46.02
5	5	5	DefaultTab		Administrator	2018-09-14 10:39:46.023
6	6	6	DefaultTab		Administrator	2018-09-14 10:39:46.023
7	7	7	DefaultTab		Administrator	2018-09-14 10:39:46.027
8	8	8	DefaultTab		Administrator	2018-09-14 10:39:46.027
9	9	9	DefaultTab		Administrator	2018-09-14 10:39:46.027
10	10	10	DefaultTab		Administrator	2018-09-14 10:39:46.027
11	11	11	DefaultTab		Administrator	2018-09-14 10:39:46.03
12	12	12	DefaultTab		Administrator	2018-09-14 10:39:46.03
13	13	13	DefaultTab		Administrator	2018-09-14 10:39:46.03
14	14	14	DefaultTab		Administrator	2018-09-14 10:39:46.03
15	15	15	DefaultTab		Administrator	2018-09-14 10:39:46.03
16	16	16	DefaultTab		Administrator	2018-09-14 10:39:46.03
17	17	17	DefaultTab		Administrator	2018-09-14 10:39:46.033
18	18	18	DefaultTab		Administrator	2018-09-14 10:39:46.4
19	19	19	DefaultTab		Administrator	2018-09-14 10:39:46.423



If you use Advanced Preview then you need to enter a SQL query in the space provided and click  to preview the data.

Previewing Data

Advanced Preview Records

```
SELECT [CAT_DIALOG_TAB_ID],[CAT_DIALOG_PROFILE_ID],[CAT_DIALOG_TAB_NAME],[CAT_DIALOG_TAB_PROPERTIES],[CREATED_BY],[CREATED_DATE_TIME],[LAST_MODIFIED_BY],[LAST_MODIFIED_DATE_TIME] FROM dbo.CAT_DIALOG_TAB
```

Preview Data

System Name:A_System
Environment Name:A_Environment

#	CAT_DIALOG_TAB_ID	CAT_DIALOG_PROFILE_ID	CAT_DIALOG_TAB_NAME	CAT_DIALOG_TAB_PROPERTIES	CREATED_BY	CREATED_DATE_TIME	I
1	1	1	DefaultTab		Administrator	2018-09-14 10:39:46.02	
2	2	2	DefaultTab		Administrator	2018-09-14 10:39:46.02	
3	3	3	DefaultTab		Administrator	2018-09-14 10:39:46.02	
4	4	4	DefaultTab		Administrator	2018-09-14 10:39:46.02	
5	5	5	DefaultTab		Administrator	2018-09-14 10:39:46.023	
6	6	6	DefaultTab		Administrator	2018-09-14 10:39:46.023	
7	7	7	DefaultTab		Administrator	2018-09-14 10:39:46.027	
8	8	8	DefaultTab		Administrator	2018-09-14 10:39:46.027	
9	9	9	DefaultTab		Administrator	2018-09-14 10:39:46.027	
10	10	10	DefaultTab		Administrator	2018-09-14 10:39:46.027	
11	11	11	DefaultTab		Administrator	2018-09-14 10:39:46.03	
12	12	12	DefaultTab		Administrator	2018-09-14 10:39:46.03	
13	13	13	DefaultTab		Administrator	2018-09-14 10:39:46.03	

Performing Table Gap Analysis

You can perform a table gap analysis and find:

- Tables not being used in mappings
- Tables existing on mapping without valid source or target


You can perform table gap analysis at the following levels:

- System
- Environment
- Table

To perform table gap analysis, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click a project.


The Metadata Tree View pane appears on the right.



3. In the **Metadata Tree View** pane, you can right-click a:
 - System: Use this option to run the analysis on all the tables under a system.
 - Environment: Use this option to run the analysis on all the tables under an environment.
 - Table: Use this option to run the analysis on a table.

Performing Table Gap Analysis


For example, the following image displays the available options when you right-click a system.



4. Click **Table Gap Analysis**.

The Table Gap Analysis page appears.

Performing Table Gap Analysis



5. Select projects and mappings.

6. Click .

The Table Gap Analysis Report for the selected projects and mappings appears.

Performing Table Gap Analysis

Table Gap Analysis

Export:

Development Team

Table Gap Analysis Report

Table Gap Analysis Result For PROJECT(S) : AdventureWorks_Migration

Tables not being used on any mapping

#	System Name	Environment Name	Table Name
1	Erwin_Sales	Integration	dbo.RM_RESOURCE
2	Erwin_Sales	Integration_Target	dbo.RM_RESOURCE
3	Erwin_Sales	N_Environment	dbo.RM_PROJECT
4	Erwin_Sales	N_Environment	dbo.RM_RESOURCE

Tables existing on Mapping without valid Source (or) Target

#	System Name	System Env Name	Table Name	Project Name	Map Name	Usage
---	-------------	-----------------	------------	--------------	----------	-------

No Records Found

Performing Column Gap Analysis

A column gap analysis enables you to find:

- Columns not existing in mappings
- Source columns existing on mappings without valid target
- Target columns listed on mappings without business rule and source column

You can perform column gap analysis at the following levels:

- System
- Environment
- Table

To perform column gap analysis, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click a project.

The Metadata Tree View pane appears on the right.


The screenshot shows the Mapping Manager interface. On the left is the 'Workspace Mappings' pane with a tree view of 'Mappings', 'Transformations', and 'Projects'. The 'Projects' list includes: ABC (3), batter (0), Del (0), dgfd (0), DigitalAdoption (4), erwinDIS (7), ffgg (2), FlowTest (3), Hi-Tunes (2), Lineage Demo (14), and a selected 'Project (4)'. On the right is the 'Mapping Summary' pane, which has tabs for 'Mapping Summary', 'Project Details', 'Project Documents', 'Project Users', and 'Project Roles'. Below the tabs is a 'Mapping Search' field and a 'Mapping Details' table.

#	Project Name	Subject Hierarchy	Map Name	Lock Status
1	Project	<input type="text"/>	Data Integration	
2	Project		DragDrop	
3	Project		SalesforceIntegration	
4	Project		TechPubs	

Performing Column Gap Analysis

3. In the **Metadata Tree View** pane, you can right-click a:
 - System: Use this option to run the analysis on all the columns under a system.
 - Environment: Use this option to run the analysis on all the columns under an environment.
 - Table: Use this option to run the analysis on all the columns under a table.


For example, the following image displays the available options when you click a system.



4. Click **Column Gap Analysis**.

The Column Gap Analysis page appears.

Performing Column Gap Analysis



5. Select projects and mappings.

6. Click .

The Column Gap Analysis Report for the selected projects and mappings appears.

Performing Column Gap Analysis

Development Team

Export:

Column Gap Analysis Report

Column Gap Analysis Result For PROJECT(S) : Erwin_Sales

Columns not existing on any Mapping

#	System Name	Environment Name	Table Name	Column Name
1	Erwin_Sales	Integration_Target	dbo.RM_RESOURCE	RESOURCEID
2	Erwin_Sales	Integration_Target	dbo.RM_RESOURCE	RESOURCENAME
3	Erwin_Sales	Integration_Target	dbo.RM_RESOURCE	RESOURCEDESC
4	Erwin_Sales	Integration_Target	dbo.RM_RESOURCE	RESOURCECELLPHONE
5	Erwin_Sales	Integration_Target	dbo.RM_RESOURCE	RESOURCEHOMEPHONE
6	Erwin_Sales	Integration_Target	dbo.RM_RESOURCE	RESOURCEEMAIL
7	Erwin_Sales	N_Environment	dbo.RM_PROJECT	PROJECTID
8	Erwin_Sales	N_Environment	dbo.RM_PROJECT	RESOURCEID
9	Erwin_Sales	N_Environment	dbo.RM_PROJECT	PROJECTNAME
10	Erwin_Sales	N_Environment	dbo.RM_PROJECT	PROJECTDESC
11	Erwin_Sales	N_Environment	dbo.RM_RESOURCE	RESOURCE_ID
12	Erwin_Sales	N_Environment	dbo.RM_RESOURCE	RESOURCENAME
13	Erwin_Sales	N_Environment	dbo.RM_RESOURCE	RESOURCEDESC
14	Erwin_Sales	N_Environment	dbo.RM_RESOURCE	RESOURCECELLPHONE
15	Erwin_Sales	N_Environment	dbo.RM_RESOURCE	RESOURCEHOMEPHONE
16	Erwin_Sales	N_Environment	dbo.RM_RESOURCE	RESOURCEEMAIL

Source Columns existing on Mapping without valid Target (with or without BR) (or) Target Columns listed on Mapping without BR (Without Source Col)

#	System Name	Environment	Table Name	Column Name	Project Name	Map Name	Usage
No Records Found							

© 2018 erwin, Inc. All rights reserved Page 1 of 1

Running Impact Analysis

A technical asset may act as a source, target, or both in mappings. After mapping source metadata to target metadata, you can run impact analysis on the technical assets. Impact analysis helps you understand upstream and downstream dependencies of technical assets and their impacts linked to business assets. It helps you assess the impact of transformations and source or target-level changes. Apart from this, you can also, view lineages based on selected assets and export its impact analysis.

You can run impact analysis at the following levels:

- [System](#)
- [Environment](#)
- [Table](#)
- [Column](#)

Running Lineage Analysis

After mapping source metadata with target metadata, you can run the lineage analyzer on the mapping through the Mapping Specification grid. The generated data lineage report helps you trace the data's origin, its transformations, and its destination after source to target mappings.

You can run the lineage at the following levels:

- [System](#)
- [Environment](#)
- [Table](#)
- [Column](#)

System

You can run forward and reverse lineage analysis to trace metadata at the system level. Forward lineage analysis generates lineage with the system as source. And, reverse lineage analysis generates lineage with the system as target. The Dual-Combined View lineage analysis generates a lineage, which includes both forward and reverse lineage.

This topic walks you through the following:


- [Viewing Lineage](#)
- [Working on Lineage](#)

Viewing Lineage

To run lineage at the system level, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click the required mapping.

The Mapping Specification grid appears.



#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision	Target Column Scale	Target Column Nullable Flag
1	SQLTechPubs	SQLTechPubs	dbo.Customers	CustomerID	nchar	5	0	0	<input type="checkbox"/>
2	SQLTechPubs	SQLTechPubs	dbo.Customers	CompanyName	nvarchar	40	0	0	<input type="checkbox"/>
3	SQLTechPubs	SQLTechPubs	dbo.Customers	ContactName	nvarchar	30	0	0	<input checked="" type="checkbox"/>
4	SQLTechPubs	SQLTechPubs	dbo.Customers	ContactTitle	nvarchar	30	0	0	<input checked="" type="checkbox"/>
5	SQLTechPubs	SQLTechPubs	dbo.Customers	Address	nvarchar	60	0	0	<input checked="" type="checkbox"/>
6	SQLTechPubs	SQLTechPubs	dbo.Customers	City	nvarchar	15	0	0	<input checked="" type="checkbox"/>


3. Select a row.

System

4. Right-click a system and hover over **Lineage Analyzer**.

The options available for Lineage Analyzer appear.

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length
1	SQLTechPubs	SQLTechPubs	dbo.Customers	CustomerID	nchar	5
2	SQLTechPubs	SQLTechPubs	dbo.Customers	CompanyName	nvarchar	40
3	SQLTechPubs	SQLTechPubs	dbo.Customers	ContactName	nvarchar	30
4	SQLTechPubs	SQLTechPubs	dbo.Customers	Address	nvarchar	60




5. Hover over any one of the following:
 - **Forward:** Use this option to view forward lineage.
 - **Reverse:** Use this option to view reverse lineage.
 - **Dual - Combined View:** Use this option to view combined forward and reverse lineage.

For example, when you hover over Forward, All Projects and By Project appear as options.

System

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length
1	SQLTechPubs	SQLTechPubs	dbo.Customers	CustomerID	nchar	5
2	SQLTechPubs	SQLTechPubs	dbo.Customers	CompanyName	nvarchar	40
3	SQLTechPubs	SQLTechPubs	dbo.Customers	ContactName	nvarchar	30
4	SQLTechPubs	SQLTechPubs	dbo.Customers	Address	nvarchar	70



6. Use the following options:


All Projects


Use this option to include all the projects in lineage analysis.

By Project


Use this option to select projects for lineage analysis.

System



By default, all projects are selected. Clear the check boxes for the projects that are not required. Then, click .

The system's forward lineage is generated based on the options you selected. Similarly, you can generate reverse, and dual lineage for a system. By default, the lineage appears in Graphical View.




7. You can click **Graphical View** or **Grid View** to switch between them:

- **Graphical View:** The graphical view displays the lineage of a system in a graphical format. Selecting a system on the graphical view displays its properties in the Node Properties pane and Legends.

On the Node Properties pane, click  to view the selected object's properties

in a new window.



- Grid View:** The grid view displays the lineage of a system in a tabular format. You can view the source and target system associated with the selected system.


#	Source System Name	Target System Name
1	TABLEUAU	SQLTechPubs
2	Informatica	Informatica
3	SQL System	SQL System
4	SQL System	SQLTechPubs
5	erwin DM	erwin DM
6	SAP	SAP

8. Use the following options to work on the lineage in graphical view:

Options (⚙️)

Use this option to view lineage types, business properties and customizations options. For more information on lineage options, refer to the [Working on](#)

[Lineage](#) section.



Export to Image (🖨️)

Use this option to download the lineage view as an image, in the .jpg format. Ensure that you expand the required nodes in a lineage before downloading the lineage image.

Export to PDF (📄)


Use this option to download the lineage report in the .pdf format. Ensure that you expand the required nodes in a lineage before downloading the lineage report as PDF.

Export to Excel (📊)

Use this option to download the lineage report in the .xlsx format. Ensure that you expand the required nodes in a lineage before downloading the report.

On the lineage, expand a system node, and select an environment to view its lineage path. The environment is highlighted in orange color, its forward lineage path appears in red, and its reverse lineage path appears in blue. Systems that are not part of a lineage path disappear.

System



Right-click a path around the selected object to highlight its path of the source or target in the lineage.


Working on Lineage

Lineage of a system shows how metadata moves through systems. It provides a summary of environments used as source and target in a graphical view. Also, it gives you information about the systems and environments involved in the lineage.

Use the following options to work on lineage:

Forward Lineage


Use this option to view forward lineage of the system.



Reverse Lineage


Use this option to view reverse lineage of the system.

System




Dual Lineage


Use this option to view dual lineage, which includes both forward and reverse lineage of the system.



Sensitivity Indicator

Use this option to view sensitivity of the environments in the lineage. You can expand a system node to view sensitive environments. The sensitive system and environments are indicated using .


System



Logical Name

Use this option to view expanded logical names of the tables and columns in an environment in the lineage. You can expand a system node to view environments and tables.


For example, the following image displays the table's logical name in the lineage.



Expanded Logical Name

Use this option to view expanded logical names of the tables and columns in an environment in the lineage. You can expand a system node to view environments, tables, and columns. For more information, on configuring extended properties of a system, refer to the [System](#) topic

For example, the following image displays the table's expanded logical name in the lineage.




DQ Tool Score

Use this option to view the data quality score of the environments, tables, and columns in the lineage. You can expand a system node to view data quality scores for environments, tables, and columns.

For example, the following image displays the data quality score in the lineage.

System




Auto Layout

Use this option to rearrange the layout of the lineage automatically.

For example, the following image displays the rearranged object layout with respect to the previous screenshot.

System




Overview Lineage

Use this option to view the lineage excluding systems and environments that do not exist in the Metadata Manager. When this option is switched off, the views include systems and environments, that do not exist in the Metadata Manager.

For example, the following image displays lineage excluding assets that do not exist in Metadata Manager.

System



Overview Pane

Use this option to remove the lineage overview pane from the graphical view.

Environment

You can run forward and reverse lineage analysis to trace metadata at the environment level. Forward lineage analysis generates lineage with the environment as source. And, reverse lineage analysis generates lineage with the environment as target. The Dual-Combined View lineage analysis generates a lineage, which includes both forward and reverse lineage.

This topic walks you through the following:

- [Viewing Lineage](#)
- [Working on Lineage](#)

Viewing Lineage

To run lineage at the environment level, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click the required mapping.

The Mapping Specification grid appears.

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision	Target Column Scale	Target Column Nullable Flag	Target Column Visible
1	SQLTechPubs	SQLTechPubs	dbo.Customers	CustomerID	nchar	5	0	0	<input type="checkbox"/>	
2	SQLTechPubs	SQLTechPubs	dbo.Customers	CompanyName	nvarchar	40	0	0	<input type="checkbox"/>	
3	SQLTechPubs	SQLTechPubs	dbo.Customers	ContactName	nvarchar	30	0	0	<input checked="" type="checkbox"/>	
4	SQLTechPubs	SQLTechPubs	dbo.Customers	ContactTitle	nvarchar	30	0	0	<input checked="" type="checkbox"/>	
5	SQLTechPubs	SQLTechPubs	dbo.Customers	Address	nvarchar	60	0	0	<input checked="" type="checkbox"/>	
6	SQLTechPubs	SQLTechPubs	dbo.Customers	City	nvarchar	15	0	0	<input checked="" type="checkbox"/>	


3. Select a row.

Environment

4. Right-click an environment and hover over **Lineage Analyzer**.

The options available for Lineage Analyzer appear.

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Length
1	SQLTechPubs	SQLTechPubs	dbo.Customers	CustomerID	nchar	5
2	SQLTechPubs	SQLTechPu		yName	nvarchar	40
3	SQLTechPubs	SQLTechPu		name	nvarchar	30
4	SQLTechPubs	SQLTechPu				




5. Hover over any one of the following:

- **Forward:** Use this option to view forward lineage.
- **Reverse:** Use this option to view reverse lineage.
- **Dual - Combined View:** Use this option to view combined forward and reverse lineage.

For example, when you hover over Reverse, All Projects and By Project appear as options.

Environment

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision
1	SQLTechPubs	SQLTechPubs	dbo.Customers	CustomerID	nchar	5	0
2	SQLTechPubs	SQLTechPubs	dbo.Address	Address	nvarchar	40	0
3	SQLTechPubs	SQLTechPubs	dbo.Address	Address	nvarchar	30	0
4	SQLTechPubs	SQLTechPubs	dbo.Address	Address	nvarchar	30	0




6. Use the following options:

All Projects


Use this option to include all the projects in lineage analysis.

By Project


Use this option to select projects for lineage analysis.



Environment


By default, all projects are selected. Clear the check boxes for the projects that are not required. Then, click .


The environment's reverse lineage is generated based on the options you selected. Similarly, you can generate forward, and dual lineage for an environment. By default, the lineage appears in Graphical View.



7. You can click **Graphical View** or **Grid View** to switch between them:

- **Graphical View:** The graphical view displays the lineage of the environment in a graphical format. Selecting an environment on the graphical view displays its properties in the Node Properties pane and Legends.

On the Node Properties pane, click  to view the selected object's properties in a new window.



- **Grid View:** The grid view displays the lineage of the environment system in a tabular format. You can view the source and target system associated with the

selected system.


The screenshot shows a web application interface for 'SQLTechPubs'. At the top, there are tabs for 'Graphical View' and 'Grid View'. Below the tabs, the text 'Dual Lineage: SQLTechPubs -- SQLTechPubs' is displayed. A table with the following columns is shown: '#', 'Source System Name', 'Source Environment Name', 'Target System Name', and 'Target Environment Name'. The table contains five rows of data.

#	Source System Name	Source Environment Name	Target System Name	Target Environment Name
1	SQLTechPubs	SQLTechPubs	SQL System	TechPubs
2	SQL System	Northwind	SQL System	Northwind
3	SQL System	TechPubs	SQL System	Northwind
4	SQLTechPubs	SQLTechPubs	Oracle	
5	TABLEUAU		SQLTechPubs	SQLTechPubs

8. Use the following options to work on the lineage in graphical view:

Options (⚙️)

Use this option to view lineage types, business properties and customizations options. For more information on lineage options, refer to the [Working on Lineage](#) section.



Export to Image (🖨️)

Environment

Use this option to download the lineage view as an image, in the .jpg format. Ensure that you expand the required nodes in a lineage before downloading the lineage image.


Export to PDF (📄)

Use this option to download the lineage report in the .pdf format. Ensure that you expand the required nodes in a lineage before downloading the lineage report as PDF.

Export to Excel (📊)

Use this option to download the lineage report in the .xlsx format. Ensure that you expand the required nodes in a lineage before downloading the report.

On the lineage, expand a system node, and select a table to view its lineage path. The environment is highlighted in blue color, its forward lineage path appears in red, and its reverse lineage path appears in blue. Systems and environments that are not part of a lineage path disappear.



Right-click a path around the selected object to highlight its path of the source or target in the lineage.

Working on Lineage


Lineage of an environment shows how metadata moves through environments. It provides a summary of tables used as source and target. Also, it gives information about the environments and tables involved in the lineage.

Use the following options to work on lineage:

Forward Lineage


Environment

Use this option to view forward lineage of the environment.



Reverse Lineage


Use this option to view reverse lineage of the environment.




Dual Lineage


Use this option to view dual lineage, which includes both forward and reverse lineage of the environment.

Environment



Sensitivity Indicator


Use this option to view sensitivity of the environments in the lineage. You can expand the environment node to view sensitive tables. The sensitive assets are indicated using .



Logical Name

Use this option to view expanded logical names of the tables and columns in an environment in the lineage. You can expand a system node to view environments and tables.

For example, the following image displays the table's logical name in the lineage.




Expanded Logical Name

Use this option to view expanded logical names of the tables and columns in an environment in the lineage. You can expand a system node to view environments, tables, and columns.

For example, the following image displays the table's expanded logical name in the lineage.


Environment



DQ Tool Score

Use this option to view the data quality score of the environments, tables, and columns in the lineage. You can expand a system node to view data quality scores for environments, tables, and columns.


For example, the following image displays the data quality score in the lineage.



Auto Layout

Environment


Use this option to rearrange the layout of the lineage automatically.
For example, the following image displays the rearranged object layout with respect to the previous screenshot.



Overview Lineage

Use this option to view the lineage excluding systems and environments that do not exist in the Metadata Manager. When this option is switched off, the views include systems and environments, that do not exist in the Metadata Manager.

For example, the following image displays lineage excluding assets that do not exist in Metadata Manager.



Overview Pane

Use this option to remove the overview pane from the graphical view.

Table

You can run forward and reverse lineage analysis to trace metadata at the table level. Forward lineage analysis generates lineage with the table as source. And, reverse lineage analysis generates lineage with the table as target. The Dual-Combined View lineage analysis generates a lineage, which includes both forward and reverse lineage.

This topic walks you through the following:

- [Viewing Lineage](#)
- [Working on Lineage](#)

Viewing Lineage

To run lineage at the table level, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click the required mapping.

The Mapping Specification grid appears.

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision	Target Column Scale	Target Column Nullable Flag
1	SQLTechPubs	SQLTechPubs	dbo.Customers	CustomerID	nchar	5	0	0	<input type="checkbox"/>
2	SQLTechPubs	SQLTechPubs	dbo.Customers	CompanyName	nvarchar	40	0	0	<input type="checkbox"/>
3	SQLTechPubs	SQLTechPubs	dbo.Customers	ContactName	nvarchar	30	0	0	<input checked="" type="checkbox"/>
4	SQLTechPubs	SQLTechPubs	dbo.Customers	ContactTitle	nvarchar	30	0	0	<input checked="" type="checkbox"/>
5	SQLTechPubs	SQLTechPubs	dbo.Customers	Address	nvarchar	60	0	0	<input checked="" type="checkbox"/>
6	SQLTechPubs	SQLTechPubs	dbo.Customers	City	nvarchar	15	0	0	<input checked="" type="checkbox"/>


3. Select a row.

Table

4. Right-click a table and hover over **Lineage Analyzer**.

The options available for Lineage Analyzer appear.

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length	Target Precision
1	SQLTechPubs	SQLTechPubs	dbo.Customers	CustomerID	nchar	5	0
2	SQLTechPubs	SQLTechPubs	dbo.Custome			40	0
3	SQLTechPubs	SQLTechPubs	dbo.Custome			30	0
4	SQLTechPubs	SQLTechPubs	dbo.Custome				



The screenshot shows a table with columns: #, Target System Name, Target Environment Name, Target Table Name, Target Column Name, Target Column Data Type, Target Column Length, and Target Precision. The table contains four rows of data. A context menu is open over the fourth row, listing options: Font Color, Font Styles, Background Color, Font Size, Clear Formatting, Impact Analysis Report, Lineage Analyzer (highlighted), Extended Properties, and Share Link. A secondary menu is open over 'Lineage Analyzer', listing: Forward, Reverse, and Dual - Combined View.

5. Hover over any of the following:

- **Forward:** Use this option to view forward lineage.
- **Reverse:** Use this option to view reverse lineage.
- **Dual - Combined View:** Use this option to view combined forward and reverse lineage.

For example, when you hover over Dual - Combined View, All Projects and By Project appear as options.

Table

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision	Target Column Scale
1	SQLTechPubs	SQLTechPubs	dbo.Customers	CustomerID	nchar	5	0	0
2	SQLTechPubs	SQLTechPubs	dbo.Customers	CustomerName	nchar	40	0	0
3	SQLTechPubs	SQLTechPubs	dbo.Customers	CustomerAddress	nvarchar	30	0	0
4	SQLTechPubs	SQLTechPubs	dbo.Customers	CustomerCity	nchar	30	0	0
5	SQLTechPubs	SQLTechPubs	dbo.Customers	Address	nvarchar	60	0	0


6. Use the following options:


All Projects

Use this option to include all the projects in lineage analysis.

By Project


Use this option to select projects for lineage analysis.




By default, all projects are selected. Clear the check boxes for the projects that are not required. Then, click .


Table

The table's dual lineage is generated based on the options you selected. Similarly, you can generate forward, and reverse lineage for tables. By default, the lineage appears in Graphical View.



7. You can click **Graphical View** or **Grid View** to switch between them:
 - **Graphical View:** The graphical view displays the lineage of the table in a graphical format. Selecting a table on the graphical view displays its properties in the Node Properties pane and Legends. On the Node Properties pane, click  to view the selected object's properties in a new window. For more information on updating table properties, refer to the [Updating Table Properties](#) topic.

Table



- Grid View:** The grid view displays the lineage of the table in a tabular format. You can view the source and target system associated with the selected system.

The grid view displays the lineage of the 'dbo.Customers' table in a tabular format. The table shows the source and target systems, environments, table names, and column names for each lineage entry.


#	Source System Name	Source Environment Name	Source Table Name	Source Column Name	Target System Name	Target Environment Name	Target Table Name	Target Column
1	erwinDoc	erwinDOC	CustDetails		TABLEUAU			
2	Oracle				Salesforce	TechPubs	Account	
3	SQLTechPubs	SQLTechPubs	dbo Customers	Address	Oracle			
4	TABLEUAU				SQLTechPubs	SQLTechPubs	dbo.Customers	ContactName
5	SQLTechPubs	SQLTechPubs	dbo Customers	ContactName	Oracle			
6	SQLTechPubs	SQLTechPubs	dbo Customers	Region	Oracle			
7	TABLEUAU				SQLTechPubs	SQLTechPubs	dbo.Customers	CompanyName

- Use the following options to work on the lineage in graphical view:

Options (⚙️)

Use this option to view lineage types, business properties and customizations options. For more information on lineage options, refer to the [Working on](#)

[Lineage](#) section.



Export to Image (🖼️)

Use this option to download the lineage view as an image, in the .jpg format. Ensure that you expand the required nodes in a lineage before downloading the lineage image.

Export to PDF (📄)


Use this option to download the lineage report in the .pdf format. Ensure that you expand the required nodes in a lineage before downloading the lineage report as PDF.

Export to Excel (📊)

Use this option to download the lineage report in the .xlsx format. Ensure that you expand the required nodes in a lineage before downloading the report.



On the lineage, expand a table node, and select a column to view its lineage path. The column is highlighted in blue color, its forward lineage path appears in red, and its reverse lineage path appears in blue. The assets that are not part of a lineage path disappear.

Table



Click a path around the selected object to highlight its path of the source or target in the lineage.

Viewing Transformations

Transformations between columns are indicated using  in the lineage. Hover over  to view transformation rules for the columns on a pop-up. Or, click the path between the columns to highlight it to view detailed transformations between them in the Transformation Details pane.

Table

The screenshot displays a data mapping tool interface. On the left, a tree view shows a project named 'SQLTechPubs' containing a table 'dbo.Customers' with a 'CustomerID' column. A transformation node is expanded, showing the following properties:

Map ID	104
Project Name	erwinDIS
Map Name	erwinSalesIntegration
Map Spec Version	1.01
Source Extract SQL	
Source column Name	customerid
Source Column Data Type	nchar
Source Column Precision	0
Source Column Length	5
Source Column Scale	0
Target column Name	OPER
Target Column Data Type	NUMBER
Target Column Precision	
Target Column Length	
Target Column Scale	
Business Rule	TRUNC
Extended Business Rule	
Trans lookup Condition	SELECT CustomerID FROM dbo.Customers WHERE CustomerID = dbo.Customers.CustomerID
Lookup On	CustomerID
Map Sequence Id	924

The right-hand sidebar shows 'Node Properties' and 'Transformation Details'. The 'Transformation Details' section lists the following properties and values:

Property	Value
Project Name	Project Tech Pubs
Map Name	erwinSalesIntegration
Map Spec Vers	1.01
JOB_XREF	
Source Extract	
Source column	customerid

You can expand the transformation node to view the transformation details that includes Business Rule, Extended Business Rule, Trans lookup Condition, Lookup On, and more relevant properties.

Working on Lineage


Lineage of a table shows how metadata moves through tables. It provides a summary of columns used as source and target. Also, it gives you information about the technical and business properties of columns involved in the lineage.

Use the following options to work on lineage:

Forward Lineage


Use this option to view forward lineage of the table.

Table



Reverse Lineage


Use this option to view reverse lineage of the table.




Dual Lineage

Table


Use this option to view dual lineage, which includes both forward and reverse lineage of the table.



Sensitivity Indicator

Use this option to view sensitivity of the table in the lineage. You can expand the table node to view sensitive columns. The sensitive assets are indicated using .

Table




Logical Name

Use this option to view expanded logical names of the tables and columns in an environment in the lineage. You can expand a system node to view environments and tables.

For example, the following image displays the table's logical name in the lineage.

Table




Expanded Logical Name

Use this option to view expanded logical names of the tables and columns in an environment in the lineage. You can expand a system node to view environments, tables, and columns. For more information on configuring extended properties of tables, refer to the [Table](#) topic.

For example, the following image displays the table's expanded logical name in the lineage.

Table




DQ Tool Score

Use this option to view the data quality score of the environments, tables, and columns in the lineage. You can expand a system node to view data quality scores for environments, tables, and columns.


For example, the following image displays the data quality score in the lineage.

Table



Auto Layout

Use this option to rearrange the layout of the lineage automatically. For example, the following image displays the rearranged object layout with respect to the previous screenshot.




Table

Overview Lineage

Use this option to view the lineage excluding systems and environments that do not exist in the Metadata Manager. When this option is switched off, the views include systems and environments, that do not exist in the Metadata Manager.

For example, the following image displays lineage excluding assets that do not exist in Metadata Manager.



Overview Pane

Use this option to remove the lineage overview pane from the graphical view.

Column

You can run forward and reverse lineage analysis to trace metadata at the column level. Forward lineage analysis generates a lineage with the column as source. And, reverse lineage analysis generates a lineage with the column as target. The Dual-Combined View lineage analysis generates a lineage, which includes both forward and reverse lineage.

This topic walks you through the following:

- [Viewing Lineage](#)
- [Working on Lineage](#)

Viewing Lineage

To run lineage at the column level, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click the required mapping.

The Mapping Specification grid appears.

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision	Target Column Scale	Target Column Nullable Flag
1	SQLTechPubs	SQLTechPubs	dbo.Customers	CustomerID	nchar	5	0	0	<input type="checkbox"/>
2	SQLTechPubs	SQLTechPubs	dbo.Customers	CompanyName	nvarchar	40	0	0	<input type="checkbox"/>
3	SQLTechPubs	SQLTechPubs	dbo.Customers	ContactName	nvarchar	30	0	0	<input checked="" type="checkbox"/>
4	SQLTechPubs	SQLTechPubs	dbo.Customers	ContactTitle	nvarchar	30	0	0	<input checked="" type="checkbox"/>
5	SQLTechPubs	SQLTechPubs	dbo.Customers	Address	nvarchar	60	0	0	<input checked="" type="checkbox"/>
6	SQLTechPubs	SQLTechPubs	dbo.Customers	City	nvarchar	15	0	0	<input checked="" type="checkbox"/>


3. Select a row.

Column

4. Right-click a column and hover over **Lineage Analyzer**.

The options available for Linear Analyzer appear.

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision	Target Column Scale
1	SQLTechPubs	SQLTechPubs	dbo.Customers	CustomerID	nchar	5	0	0
2	SQLTechPubs	SQLTechPubs	dbo.Customers	CompanyNi			0	0
3	SQLTechPubs	SQLTechPubs	dbo.Customers	ContactNam			0	0
4	SQLTechPubs	SQLTechPubs	dbo.Customers	ContactTitle				
5	SQLTechPubs	SQLTechPubs	dbo.Customers	Address	nvarchar	60	0	0




5. Hover over any one of the following:

- **Forward:** Use this option to view forward lineage.
- **Reverse:** Use this option to view reverse lineage.
- **Dual - Combined View:** Use this option to view forward and reverse lineage of the column combined together.

For example, when you hover over the Reverse, All Projects and By Project appear as options.

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision	Target Column Scale
1	SQLTechPubs	SQLTechPubs	dbo.Customers	CustomerID	nchar	5	0	0
2	SQLTechPubs	SQLTechPubs	dbo.Customers	C		40	0	0
3	SQLTechPubs	SQLTechPubs	dbo.Customers	C		30	0	0
4	SQLTechPubs	SQLTechPubs	dbo.Customers	C				



Column


6. Use the following options:


All Projects

Use this option to include all the projects in lineage analysis.

By Project


Use this option to select projects for lineage analysis.




By default, all the projects are selected. Clear the check boxes for the projects that are not required. Then, click .


The column's reverse lineage is generated based on the options you selected. Similarly, you can generate forward, and dual lineage for columns. By default,

the lineage appears in Graphical View.



7. You can click **Graphical View** or **Grid View** to switch between them:
 - **Graphical View:** The graphical view displays the lineage of the column in a graphical format. Selecting a column on the graphical view displays its properties in the Node Properties pane and Legends. On the Node Properties pane, click  to view the selected object's properties in a new window. For more information on updating column properties, refer to the [Updating Column Properties](#) topic.

Column



- **Grid View:** The grid view displays the lineage of the environment system in a tabular format. You can view the source and target system associated with the selected system.

The grid view displays the lineage of the environment system in a tabular format. The table below shows the source and target systems associated with the selected system.


#	Info	Source System Name	Source Environment Name	Source Table Name	Source Column Name	Target System Name	Target Environment Name
1		TABLEUAU	PRESENTATION LAYER	Account	Acct Atm Status	SQLTechPubs	SQLTechPubs
2		SQLTechPubs	SQLTechPubs	dbo.Customers	CustomerID	Oracle	TechPubs
3		Oracle	TechPubs	APPQOSSYS.WLM_CLA SSIFIER_PLAN		Salesforce	TechPubs

8. Use the following options to work on the lineage in graphical view:

Options (⚙️)

Use this option to view lineage types, business properties and customizations options. For more information on lineage options, refer to the [Working on](#)

[Lineage](#) section.



Export to Image (🖨️)

Use this option to download the lineage view as an image, in the .jpg format. Ensure that you expand the required nodes in a lineage before downloading the lineage image.

Export to PDF (📄)


Use this option to download the lineage report in the .pdf format. Ensure that you expand the required nodes in a lineage before downloading the lineage report as PDF.

Export to Excel (📊)

Use this option to download the lineage report in the .xlsx format. Ensure that you expand the required nodes in a lineage before downloading the report.



On the lineage, expand a table node, and select a column to view its lineage path. The column is highlighted in blue color, its forward lineage path appears in red, and its reverse lineage path appears in blue. Assets that are not part of a lineage path disappear.

Column



Right-click a path around the selected object to highlight its path of the source or target in the lineage.

Viewing Transformations

Transformations between columns are indicated using  in the lineage. Hover over  to view transformation rules for the columns on a pop-up. Or, click the path between the columns to highlight it to view detailed transformations between them in the Transformation Details pane.

Column

The screenshot displays the SSDT interface for a column transformation. On the left, a project tree shows 'SQLTechPubs' and 'dbo.Customers'. The center pane shows the transformation node's properties, including source and target column names, data types, and a SQL query. The right pane shows the 'Node Properties' and 'Transformation Details' for the selected node.

Property	Value
Map ID	104
Project Name	erwinDIS
Map Name	erwinSalesIntegration
Map Spec Version	1.01
Source Extract SQL	
Source column Name	customerid
Source Column Data Type	nchar
Source Column Precision	0
Source Column Length	5
Source Column Scale	0
Target column Name	OPER
Target Column Data Type	NUMBER
Target Column Precision	
Target Column Length	
Target Column Scale	
Business Rule	TRUNC
Extended Business Rule	
Trans lookup Condition	SELECT CustomerID FROM dbo.Customers WHERE CustomerID = dbo.Customers.CustomerID
Lookup On	CustomerID
Map Sequence Id	924

You can expand the transformation node to view the transformation details that includes Business Rule, Extended Business Rule, Trans lookup Condition, Lookup On, and more relevant properties.

Working on Lineage


Lineage of a column shows how metadata moves through columns. It provides a summary of columns used as source and target. Also, it gives information about technical and business properties of columns involved in the lineage.

Use the following options to work on lineage:

Forward Lineage


Use this option to view forward lineage of the column.

Column



Reverse Lineage


Use this option to view reverse lineage of the column.



Column

Dual Lineage

Use this option to view dual lineage, which includes both forward and reverse lineage of the column.




Sensitivity Indicator

Use this option to view sensitivity of the columns in the lineage. You can expand the environment node to view sensitive columns. The sensitive assets are indicated using



Column




Logical Name

Use this option to view expanded logical names of the tables and columns in an environment in the lineage. You can expand a system node to view environments and tables.

For example, the following image displays the table's logical name in the lineage.

Column




Expanded Logical Name

Use this option to view expanded logical names of the tables and columns in an environment in the lineage. You can expand a system node to view environments, tables, and columns. or more information on configuring extended properties of columns, refer to the [Column](#) topic.

For example, the following image displays the table's expanded logical name in the lineage.


Column



DQ Tool Score

Use this option to view the data quality score of the environments, tables, and columns in the lineage. You can expand a system node to view data quality scores for environments, tables, and columns.


For example, the following image displays the data quality score in the lineage.



Column

Auto Layout

Use this option to rearrange the layout of the lineage automatically. For example, the following image displays the rearranged object layout with respect to the previous screenshot.




Overview Lineage

Use this option to view the lineage excluding systems and environments that do not exist in the Metadata Manager. When this option is switched off, the views include systems and environments, that do not exist in the Metadata Manager.

For example, the following image displays lineage excluding assets that do not exist in Metadata Manager.

Column



Overview Pane

Use this option to remove the lineage overview pane from the graphical view.


Running End to End Lineage

You can run end to end lineage analysis at project level and trace the data between any two mapping projects. The end to end lineage report can be drilled down further to trace intermediate stages of data.

To run end to end lineage at project level, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, right-click the required source project.


The available options appear.




3. Click **End to End Lineage**.

Running End to End Lineage

The Select Target page appears.



4. Select a target subject or a target project.
5. Click .

Running End to End Lineage

The End to End Lineage Summary page appears. You can drag and arrange column positions on the page for better visibility.


#	Source Project	Source Subject	Source System	Source Environment	Source Table	Source XPath	Source Column	Source User Defined-1	Source User Defined-2	Source Valid Values	Target Column	Target XPath	Target User Defined-1	Target User Defined-2
1	Project		TABLEUAU	PRESENTATION LAYER	Account		Acct Atm Status			Click Here				
2	Project		TABLEUAU	PRESENTATION LAYER	Account		Cod Acct No			Click Here				
3	Project		TABLEUAU	PRESENTATION LAYER	Account		Cod Acct No			Click Here				
4	Project		TABLEUAU	PRESENTATION LAYER	Account		Acct Prod Source Id			Click Here				
5	Project		TABLEUAU	PRESENTATION LAYER	Account		Acct Prod Source Id			Click Here				
6	Project		TABLEUAU	PRESENTATION LAYER	Account		Acct Cod Coy			Click Here				
7	Project		Oracle	TechPubs	APPOSSYS.WLM_CL		SEQNO			Click Here				
8	Project		Oracle	TechPubs	APPOSSYS.WLM_CL		TIMESTAMP			Click Here				
9	Project		TABLEUAU	PRESENTATION LAYER	Account		Acct Cod Coy			Click Here				
10	Project		Oracle	TechPubs	APPOSSYS.WLM_CL		CHKSUM			Click Here				

Use the following options to work on the End to End Lineage Summary page:

Navigate

Use  or  to navigate.

Expand

To expand the lineage summary, use . The expanded summary shows the intermediate stages of data.

End To End Lineage Details [Source: Acct Atm Status Target:]														
#	Project Name	Map Id	Map Name	Source System	Source Environmen	Source Table	Source Column	Source Valid Values	Business Rule	Extended Business Rule	Target Valid Values	Target XPath	Target Column	Target User Defined-1
1	Project	69	Data Integratic	TABLEUAU	PRESENTATI	Account	Acct Atm Status	Click Here			Click Here		CustomerID	dbo.C
2	Project Tech P	105	erwinSalesInte	SQLTechPub	SQLTechPubs	dbo.Customers	CustomerID	Click Here	TRUNC		Click Here		OPER	APPO
3	erwinDIS	66	SalesforInte	Oracle	TechPubs	APPOSSYS.WLM_CL	OPER	Click Here	UPPER		Click Here		Id	Acco

Running End to End Lineage

Reset Column Ordering (🔌)

Use this option to reset the column order on the page.

Export (📄)

Use this option to export the lineage summary in the XLSX format.


Opening Business View

You can open a concise view of mappings with an ability to instantly generate lineage and impact analysis. It is an alternate view for both workspace and published maps and more suitable for business users.

To open business view of mappings, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, right-click a map.

The available options appear.



3. Click **Mapping Alternate View**.

The Mapping Summary page appears. It has two sections, Mapping Details and Mapping Specifications.

Opening Business View

The screenshot shows the 'Mapping Summary' window. The 'Mapping Details' section includes fields for Specification Name (Erwin_Map), Version (1.00), Mapping Description (mapping description), Target Tables (dbo.ADS_New ASSOCIATIONS), Source Tables (dbo.ADS ASSOCIATIONS), SQL Query, Target Update Strategy, Graphical View (View), User Defined1-5, and Map Spec Docs (View). The 'Mapping Specification' section is a table with columns for #, Info, System, Environment, Table, Column, Data Type (L/P/S), Business Rule, Extended Business Rule, and System. It lists five rows of mappings from 'New_Erwin' to 'erwinDIS'.

Target Details						Transformations			
#	Info	System	Environment	Table	Column	Data Type (L/P/S)	Business Rule	Extended Business Rule	System
1		New_Erwin	Erwin_Environment	dbo.ADS_New_ASSOC	ID_New	bigint(8,19,0)	ABS		erwinDIS
2		New_Erwin	Erwin_Environment	dbo.ADS_New_ASSOC	SOURCE_OBJECT_ID_New	bigint(8,19,0)	ABS		erwinDIS
3		New_Erwin	Erwin_Environment	dbo.ADS_New_ASSOC	SOURCE_OBJECT_TYPE_ID	bigint(8,19,0)	ABS		erwinDIS
4		New_Erwin	Erwin_Environment	dbo.ADS_New_ASSOC	TARGET_OBJECT_ID_New	bigint(8,19,0)	ABS		erwinDIS
5		New_Erwin	Erwin_Environment	dbo.ADS_New_ASSOC	TARGET_OBJECT_TYPE_ID	bigint(8,19,0)	ABS		erwinDIS

Mapping Details

It displays mapping details that includes mapping specification name, version, target update strategy, and lists of target and source tables.

Mapping Specification

It displays the Mapping Specification grid with source and target details.

Under the Mapping Details and Mapping Specification sections, you can click a <Table_Name> or <Column_Name> to view their respective details.

Table Details

To view table details, on the **Mapping Summary** page, click <Table_Name>.

The Table Details page appears. By default, the Impact Analysis tab opens. You can view direct, indirect, and other impacts of the table.

For more information on impact analysis, refer to the [Running Impact Analysis](#) topic.

Opening Business View

The screenshot shows the 'Table Details' window for 'dbo.ADS_ASSOCIATIONS(Data_Migration.erwinDIS)'. The 'Impact Analysis' tab is active, displaying summary cards for 'Direct Impact' and 'Indirect Impact'. The 'Direct Impact' card shows 8 records as source and 0 as target. The 'Indirect Impact' card shows 0 records as source and 2 as target. A legend indicates: Green for Upstream Impact, Red for Downstream Impact, and Blue for In Business Rule. An 'Audit Information' table shows 'Created By: Administrator' and 'Created Time: 01/01/2020 11:43:01'. Below are two tables: 'As Source' and 'As Target'. The 'As Source' table has 3 rows of data, and the 'As Target' table shows 'No Records Found'.

Audit		Information	
Created By	Administrator		
Created Time	01/01/2020 11:43:01		

#	Project Name	Mapping Name	Target Information			Business Rule
			Table	Environment	System	
1	A_Project	Erwin_Map	dbo.ADS_New_ASSOCIATIONS	Data_Migration	erwinDIS	ABS
2	Erwin_Feb	Integration_Feb	dbo.RM_RESOURCE	Integration	Erwin_Sales	
3	Erwin_Project	Child_Map	dbo.ADS_New_ASSOCIATIONS	Data_Migration	erwinDIS	

#	Project Name	Mapping Name	Source Information			Business Rule
			Table	Environment	System	
No Records Found						

You can click the following tabs to work on the Table Details page:

- **Data Lineage:** This tab displays the forward and reverse lineage of the table. For more information on lineage of tables, refer to the [Table](#) topic.
- **Extended Properties:** This tab displays the extended properties configured for the table. For more information on configuring extended properties, refer to the [Extending Table Properties](#) topic.
- **Table Properties:** On this tab, you can view the table properties. For more information on table properties, refer to the [Updating Table Properties](#) topic.
- **Columns:** This tab displays a list of columns in the table.
- **Workflow Log:** This tab displays the workflow log of the table. For more information on configuring workflows, refer to the [Using Workflow Manager](#) section.
- **Data Quality:** On this tab, you can preview and profile the data in the table. For more information on previewing and profiling data, refer to the [Previewing Data](#) topic.

Opening Business View

- **Documents:** On this tab, you can view or add documents related to the table.
- **Test Specifications:** On this tab, you can view the test cases related to the table. For more information on test cases, refer to the [Creating Test Cases](#) topic.

Column Details

To view column details, on the Mapping Summary page, click <Column_ Name>.

The Column Details page appears. By default, the Impact Analysis tab opens. You can view direct, indirect, and other impacts of the column.

For more information on impact analysis, refer to the [Running Impact Analysis](#) topic.

The screenshot shows the 'Column Details' window for the column 'ID(dbo.ADS_ASSOCIATIONS.Data_Migration.erwinDIS)'. The 'Impact Analysis' tab is active, showing a summary of direct and indirect impacts. The 'As Source' section contains the following table:

#	Project Name	Mapping Name	Target Information				Business Rule
			Column	Table	Environment	System	
1	A_Project	Erwin_Map	ID_New	dbo.ADS_New_ASSOCIATIONS	Data_Migration	erwinDIS	ABS
2	Erwin_Feb	Integration_Feb	RESOURCEID	dbo.RM_RESOURCE	Integration	Erwin_Sales	
3	Erwin_Project	Child_Map	ID_New	dbo.ADS_New_ASSOCIATIONS	Data_Migration	erwinDIS	

The 'As Target' section shows 'No Records Found'.

You can click the following tabs to work on the Column Details page.

- **Data Lineage:** This tab displays the forward and reverse lineage of the column. For more information on lineage of columns, refer to the [Column](#) topic.

Opening Business View

- **Extended Properties:** This tab displays the extended properties configured for the column. For more information on configuring extended properties, refer to the [Extending Column Properties](#) topic.
- **Column Properties:** This tab displays the column properties. For more information on column properties, refer to the [Updating Column Properties](#) topic.
- **Workflow Log:** This tab displays the workflow log of the column. For more information on configuring workflows, refer to the [Using Workflow Manager](#) section.
- **Valid Values:** This tab displays the codesets assigned to the column as valid values. For more information on assigning codesets to columns, refer to the [Assigning Codesets to Columns](#) topic.
- **Documents:** This tab displays the uploaded documents related to the column.

Viewing Mapping Statistics


You can view mapping statistics and view the following information about mapping specifications:

- Total rows
- Number of target tables
- Targets not mapped
- Sources not mapped
- Business rules
- Lookups

To view mapping statistics, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click the required map.

The Mapping Specification grid appears.



#	Source System Name	Source Environment Name	Source Table Name	Source Column Name	Source Column Data Type	Source Column Length	Business Rule
1	erwinDIS	erwinDIS	dbo.ADS_ASSOCI	ID	bigint	8	ABS
2	erwinDIS	erwinDIS	dbo.ADS_ASSOCI	SOURCE_OBJECT_	bigint	8	ABS
3	erwinDIS	erwinDIS	dbo.ADS_ASSOCI	SOURCE_OBJECT_	bigint	8	ABS

3. click .

The mapping statistics are shown with hyperlinks.

Viewing Mapping Statistics

Source Column Name	Source Column Data Type	Total Rows:	6
ID	bigint	Target Tables:	1
		Source Tables:	1
		Targets Not Mapped:	0
		Sources Not Mapped:	0
SOURCE_OBJECT	bigint	Business Rules:	1
		Possible Truncations:	0
		Look Ups:	0

You can click the required hyperlinks to get the detailed information.

Associating Mappings

This section walks you through the process of associating mappings with the following:

- Code Mappings or Code Crosswalks
- Reference Tables
- Requirements

It involves:

- [Associating code maps with data item mappings](#)
- [Associating reference tables with mappings](#)
- [Linking requirements with mappings](#)

Associating Code Maps with Data Item Mappings

A code map can be associated with a data item mapping to standardize data across the organization. These code maps are maintained in Codesets Manager. For more information on codesets and code mappings, refer to the [Using Codesets Manager](#) section.


Before associating a code map with data item mappings, ensure that you publish the code map.

Publishing Code Maps

To publish code maps, follow these steps:

1. Go to **Application Menu > Data Catalog > Codeset Manager > Codeset Mappings**.
2. In the **Code Mappings Workspace** pane, right-click a code map.

The available options appear.



3. Click **Publish**.

The Publish Codeset Map page appears.

Associating Code Maps with Data Item Mappings

The screenshot shows a 'Publish Codeset Map' dialog box with the following fields and values:

- Codeset Map Name***: Integrated_Map
- Codeset Map Version**: 1.01
- Codeset Map Description**: Code map when source and target have different code values.
- Map Version Label**: (empty)
- Map Changed Description***: Updated Code Values.
- Publish Environment***: DEV, PROD, Production, Test

4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Codeset Map Name	Specifies the name of the code map. For example, Gender Crosswalk.
Codeset Map Version	Specifies the new version of the code map. For example, 1.02.
Codeset Map Description	Specifies the description about the code map. For example: The codeset map is the code mappings between the two codesets, Misc Gender Codes and Gender.
Map Version Label	Specifies the version label of the code map. For example, Beta.
Map Changed Description	Specifies the description about the changes made in the code map. For example: Code values were updated.
Publish Environment	Specifies the environment where the code map is being published. For example, test. You can create publish environments in Enterprise Codesets.


Associating Code Maps with Data Item Mappings

Field Name	Description
	For more information on creating publish environments, refer to the Publishing Codesets topic.

5. Click .

The code map is published and it can be found in the Published Code Mappings pane under the selected Publish Environment.

A new version of the code map is created under the Mappings tree.



A published code map can be associated with a mapping in the Mapping Manager. The published code map is available under the Code Mappings Catalog.

Associating Code Maps

To associate published code maps with data item mappings, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click the required map.

Associating Code Maps with Data Item Mappings

The Mapping Specification grid appears.

#	Target System Name	Target Environment Name	Target Table Name	Target Column Name	Target Column Data Type	Target Column Length
1	SQLTechPubs	SQLTechPubs	dbo.Customers	CustomerID	nchar	5
2	SQLTechPubs	SQLTechPubs	dbo.Customers	CompanyName	nvarchar	40
3	SQLTechPubs	SQLTechPubs	dbo.Customers	ContactName	nvarchar	30
4	SQLTechPubs	SQLTechPubs	dbo.Customers	ContactTitle	nvarchar	30
5	SQLTechPubs	SQLTechPubs	dbo.Customers	Address	nvarchar	60

3. Click .

4. In the **Mapping Specification** grid, right-click the header menu.

Target Table	Target Column Name	Target Column Data Type	Target Column Length	Target Column Precision	Target Column Scale	Target Column Nullable Flag
customers	PostalCode	nvarchar	10	0		
customers	City	nvarchar	15	0	0	<input checked="" type="checkbox"/>

5. Select the **CSM Mapping** check box.

The CSM Mapping Column appears in the Mapping Specification grid.

6. In the right pane, expand **Code Mapping Catalog**.

7. Drag the code map into the **Mapping Specification** grid and drop it under the **CSM Mapping** column for the required row.

Associating Code Maps with Data Item Mappings

8. Click .

The code map is associated with the data item mappings.

Associating Reference Tables with Mappings


Reference data sets the permissible values for other data fields. To standardize your data, you can associate a reference table with mappings. Ensure that you publish the required reference table before associating it with mappings.

To associate reference tables with Mappings, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click a map.

The Mapping Specification grid appears.

#	Source System Name	Source Environment Name	Source Table Name	Source Column Name	Source Column Data Type	Source Column Length	Business Rule
1	Erwin_Sales	Integration	dbo.RM_RESOURCE	RESOURCEID	int	4	FLOOR
2	Erwin_Sales	Integration	dbo.RM_RESOURCE	RESOURCENAME	varchar	100	REVERSE
3	Erwin_Sales	Integration	dbo.RM_RESOURCE	RESOURCEDESC	varchar	150	dbo.RM_Resource

3. Click .
4. Right-click the header menu.


#	Source System Name	Source Environment Name	Source Table Name	Source Column Name	Source Column Data Type	Source Column Length
1	Erwin_Sales	Integration	dbo.RM_RESOURCE			4
2	Erwin_Sales	Integration	dbo.RM_RESOURCE			100


5. Select the **Reference Table** check box.

The Reference Table column appears in the Mapping Specification grid.

Associating Reference Tables with Mappings

6. Drag the reference table from **Reference Table Catalog** and drop it on the required row under the **Reference Table** column.

 You can associate multiple source columns with the reference tables.



target Column length	Created By	Created Date	CSM Mapping	Last Modified By	Last Modified Date Time	Reference Table
	Administrator	2019-10-21 14:36:15.057	Integrated_Map(1.00)	Administrator	2019-12-10 14:49:07.187	
	Administrator	2019-10-21 14:36:15.057		Administrator	2019-12-10 14:49:07.187	

7. Click .

The reference table is associated with the mappings.

Linking Requirements to Mappings

To ensure enterprise-wide traceability, you can link your functional requirements to data mappings.

To link functional requirements to mappings, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. Click a mapping.

The mapping opens in the detailed view.

#	Source System Name	Source Environment Name	Source Table Name	Source Column Name	Source Column Data Type	Source Column Length	Business Rule
1	A_System	A_Environment	dbo.CAT_DIALOG	CAT_DIALOG_TAB	int	4	
2	A_System	A_Environment	dbo.CAT_DIALOG	CAT_DIALOG_PRC	int	4	
3	A_System	A_Environment	dbo.CAT_DIALOG	CAT_DIALOG_TAB	varchar	50	
4	A_System	A_Environment	dbo.CAT_DIALOG	CAT_DIALOG_TAB	varchar	4000	
5	A_System	A_Environment	dbo.CAT_DIALOG	CREATED_BY	varchar	50	
6	A_System	A_Environment	dbo.CAT_DIALOG	CREATED_DATE_Ti	datetime	8	

3. On the **Mapping Specification** tab, right click the grid header.


A list of header columns appears.

Linking Requirements to Mappings

#	Source System Name	Source Environment Name	Source Table	Source Column	Source Column Data Type	Source Length
1	A_System	A_Environment			nt	4
2	A_System	A_Environment			nt	4
3	A_System	A_Environment	dbo.CAT_DIALOG	CAT_DIALOG_TAB	varchar	50

4. Scroll down the list and select the **Specification Artifact** check box.
The specification Artifact column becomes visible on the Mapping Specification tab.
5. In the right pane, click **Specification Artifact Catalog**.
6. Expand the project that contains the required specification.
7. Drag and drop the specification on the **Specification Artifacts** column in the required row.

st Column Type	Target Column Length	Created By	Created Date	Specification Artifacts	Last Modified By	Last Modified Date Time
	4	Administrator	2019-10-16 15:44:32.383	Sp_Name (v1.00)	Administrator	2019-10-17 11:56:07.883
	4	Administrator	2019-10-16 15:44:32.383		Administrator	2019-10-16 15:45:28.353
ar	50	Administrator	2019-10-16 15:44:32.383		Administrator	2019-10-16 15:45:28.353

8. Click .
Requirements are linked to the selected mapping.

Publishing and Creating Versions of Mappings

This section walks you through the process of publishing mappings to corresponding source or target production environments. Production environments of the source and the target are defined in the Metadata Manager. You can also create new versions of the mappings while archiving the older versions.

It involves:

- [Creating versions of maps](#)
- [Base-lining Projects](#)
- [Comparing two different mapping versions](#)
- [Publishing mappings](#)
- [Restoring archived maps as active](#)


Creating Versions of Maps

You can create new version of maps and track history of changes made in the mapping specification. You can also notify and send mail comments to all the project users about the creation of new version. For more information on notifying project users, refer to the [Configuring Notifications](#) topic.

To create versions of maps, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, right-click a map.

The available options appear.



3. Click **New Version**.

The New Version page appears.

Creating Versions of Maps

4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Mapping Name	Specifies the mapping specification name. For example, EDW_PROD_IDS_Benefits_Detail.
Mapping Version	Specifies the new version of the mapping specification. For example, 1.02.
Mapping Description	Specifies the description about the mapping. For example: This is a map between EDW source and IDS target systems.
Version Label	Specifies the version label of the mapping specification. For example, Beta. For more information on configuring version display of mapping specifications, refer to the Configuring Version Display topic.
Changed Description	Specifies the description of the changes made in the mapping specification. For example: A business rule for a source column was added.
Mail Comments	Specifies the mail comments, which can be sent to the project users through an email notification. For example: Target update strategy is not updated.

Creating Versions of Maps


Field Name	Description
	For more information on configuring notifications, refer to the Configuring Notifications topic.

5. Click .

A new version of the map is created and the previously active version moves under the archive folder.



Archived maps are in read-only mode and cannot be edited.




Base-lining Projects

Base-lining a project brings all maps in the project to the same version. You can base-line all the maps in a project and record change description and notify all the project users and send mail comments to them.

To base-line projects, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, right-click a project.


The available options appear.



3. Click **New Baseline**.

The New Baseline page appears.

Base-lining Projects



4. Enter **Version Label**, **Change Description**, and **Mail Comments**.

For example:

- **Version Label** - Beta.

For more information on version display, refer to the [Configuring Version Display](#) topic.

- **Change Description** - Business rule for all the source column was changed to ASCII.

- **Mail Comments** - The target update strategy needs to be updated.

For more information on notifying project users, refer to the [Configuring Notifications](#) topic.

5. Click .

The project is base-lined and all the maps in the project now have the same version. Project users receive email notifications about the base-lining and mail comments, if you enable notifications for it. For more information on configuring notifications, refer to the [Configuring Notifications](#) topic.

Comparing Two Different Mapping Versions

You can use the advanced mapping comparison ability to quickly and efficiently compare any two mapping versions. You can view the changes on a row by row basis and improve your debugging ability.

To compare two different mapping versions, follow these steps:


1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, select two mapping versions.



Use shift keys to select the two mapping versions.

3. Right-click the selection.

The available options appear.



4. Click **Compare To**.

The Compare To page appears. All the changes are highlighted in red color in the comparison report.

Comparing Two Different Mapping Versions

Development Team

Map1 Name: 2-L_Customer_Dim (V6.00 / VLv5x)

Map2 Name: 2-L_Customer_Dim (V5.00 / VLv4x)

Exclude Common Rows Export:

Source Details											
Version	System	Environment	Table	Column	Data Type	Length	Precision	Scale	Definition	Comments	Logical Column Name
6.00	Jed Pty Data Files	Jed Pty Data Files	Customers	CustomerNumber	Varchar(10)	10.0			Customer Number		Customer Number
5.00	Jed Pty Data Files	Jed Pty Data Files	Customers	CustomerNumber	Varchar(10)	10.0			Customer Number		Customer Number

Source Details											
Version	System	Environment	Table	Column	Data Type	Length	Precision	Scale	Definition	Comments	Logical Column Name
6.00	Jed Pty Data Files	Jed Pty Data Files	Customers	CustomerNumber	Varchar(10)	10.0			Customer Number		Customer Number
5.00	Jed Pty Data Files	Jed Pty Data Files	Customers	CustomerNumber	Varchar(10)	10.0			Customer Number		Customer Number

Source Details											
Version	System	Environment	Table	Column	Data Type	Length	Precision	Scale	Definition	Comments	Logical Column Name
6.00	Jed Pty Data Files	Jed Pty Data Files	Customers	FirstName	Varchar(25)	25.0			First Name		First Name
5.00	Jed Pty Data Files	Jed Pty Data Files	Customers	FirstName	Varchar(25)	25.0			First Name		First Name

Source Details											
Version	System	Environment	Table	Column	Data Type	Length	Precision	Scale	Definition	Comments	Logical Column Name
6.00	Jed Pty Data Files	Jed Pty Data Files	Customers	FirstName	Varchar(25)	25.0			First Name		First Name
5.00	Jed Pty Data Files	Jed Pty Data Files	Customers	FirstName	Varchar(25)	25.0			First Name		First Name

Source Details											
Version	System	Environment	Table	Column	Data Type	Length	Precision	Scale	Definition	Comments	Logical Column Name
6.00	Jed Pty Data Files	Jed Pty Data Files	Customers	Full Address	Varchar(50)	50.0			Customer full address		Customer full address
5.00	Jed Pty Data Files	Jed Pty Data Files	Customers	Full Address	Varchar(50)	50.0			Customer full address		Customer full address

To exclude exporting common rows in the report, select **Exclude Common Rows Export**.

Use the following options to export the comparison report:

- To export the report in the PDF format, click .
- To export the report in the XLSX format, click .
- To export the report in the HTML format, click .


Publishing Mappings

You can publish a map on an effective date and enter publishing notes for a record. Before publishing mappings, ensure that the source and the target environments have their corresponding production environments.

Publishing Mappings

To publish mappings, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, right-click a map.




3. Click **Publish Map**.

The Publish Map page appears.

Publishing Mappings

4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Mapping Name	Specifies the mapping specification name. For example, EDW_PROD_IDS_Benefits_Detail. It is autopopulated and you cannot edit this field.
Mapping Version	Specifies the version of the mapping specification. For example, 1.00. It is autopopulated. For more information on configuring version display of maps, refer to the Configuring Version Display topic.
Version Label	Specifies the version label of the mapping specification. For example, EDW_PROD_IDS_Benefits_Detail (Alpha). For more information on configuring version display of maps, refer to the Configuring Version Display topic.
Effective Date	Use  to enter the effective date of publishing. For example, 04/02/2020.

Publishing Mappings

Field Name	Description
Change Description	Specifies the description for changes made in the mapping specification. For example: Business rule was modified from ABORT to ASCII for the source column ID.
Publish Notes	Specifies the publish notes about the mapping specification. For example: The mapping specification is approved for publishing on 1 Feb 2020.

5. Click .

The mapping is published on the effective date and saved in the **Published Mappings** pane. The source and the target environments in the published mapping are updated to their corresponding production environments. All previously published versions of the same mapping are stored in the History folder. A published mapping cannot be edited.

A new version of the mapping is automatically created in **Workspace Mappings** that can be edited.

To view published map details, in the **Published Mappings** pane, click the <Mapping_Name>.

The business view of the mapping appears which can be used to run impact analysis, lineage analysis, and data quality etc. For more information on business view, refer to the [Opening Business View](#) topic.

Publishing Mappings

Mapping Details

Specification Name	New_Mapping	Map Id	219
Version	1.03	Version Label	
Mapping Description			
Target Tables	dbo.ADS_ASSOCIATIONS dbo.ADS_FORM dbo.ADS_KEY_VALUE dbo.ADS_KEY_VALUE_OBJECTS	Source Tables	dbo.ADS_ASSOCIATIONS dbo.ADS_FORM dbo.ADS_KEY_VALUE dbo.ADS_KEY_VALUE_OBJECTS
SQL Query			
SQL Query Description			
Target Update Strategy			
Map Spec Docs	View		

Mapping Specification

#	Target Details				Transformations			System	
	Info	System	Environment	Table	Column	Data Type (L/P/S)	Business Rule		Extended Business Rule
1		New_System	New_Environn	dbo.ADS_KEY_VAI	OBJECT_PARENT_TYPE	varchar(500,0,0)	UPPER		New_Syst
2		New_System	New_Environn	dbo.ADS_KEY_VAI	OBJECT_PARENT_CO	varchar(500,0,0)			New_Syst
3		New_System	New_Environn	dbo.ADS_KEY_VAI	MODULE_KEY	varchar(255,0,0)			New_Syst
4		New_System	New_Environn	dbo.ADS_KEY_VAI	OBJECT_TITLE	varchar(255,0,0)			New_Syst
5		New_System	New_Environn	dbo.ADS_KEY_VAI	OBJECT_TYPE_ID	bigint(8,19,0)			New_Syst
6		New_System	New_Environn	dbo.ADS_KEY_VAI	OBJECT_TABLE	varchar(500,0,0)			New_Syst
7		New_System	New_Environn	dbo.ADS_KEY_VAI	OBJECT_TABLE_COU	varchar(500,0,0)			New_Syst

Updating Publishing Details

To update publishing details of published maps, follow these steps:

1. In the **Workspace Mappings** pane, right-click the required project.

The available options appear.


Workspace Mappings

- New Map
- Upload Legacy Maps
- UpLoad XML
- New Baseline
- Export All
- Export Mapping Manager XML
- Publish Mappings
- Edit Published Maps**
- Reports
- New Subject Area
- Reorder Subject Areas
- Share Link
- Delete Project
- Run Template
- End To End Lineage
- View Workflow

Publishing Mappings

2. Click **Edit Published Maps**.

The Edit Publish Mappings page appears. You can use **Filter by Effective Date** to filter the mappings based on the effective publishing date.



3. In the **Publish Tree** pane, select the required published map.

Now, you can update Publish Notes and Effective Date.

4. Click .


The publishing details of the map is updated.

Restoring Archived Maps As Active

When you create a new version of a map, the older version is archived. The archived map is in read-only mode and cannot be edited. You can restore an archived map as an active map and work on the map.

To restore archived maps as active, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, right-click the required archived map.



The Restoring Archived Mapping as Active page appears.

Restoring Archived Maps As Active

The screenshot shows a window titled "Restoring Archived Mapping as Active". It contains the following fields:

- Mapping Name***: A text box containing "M_Map".
- Mapping Version**: A text box containing "1.02".
- Mapping Description**: A large empty text area.
- Version Label**: A text box.
- Changed Description***: A rich text editor with a toolbar including icons for font color, bold, italic, underline, bulleted list, numbered list, indent, and outdent.
- Mail Comments**: A text box at the bottom.

3. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.


Field Name	Description
Mapping Name	Specifies the mapping specification name. For example, EDW_PROD_IDS_Benefits_Detail.
Mapping Version	Specifies the new version of the mapping specification. For example, 1.02.
Mapping Description	Specifies the description of the mapping. For example: This is a map between EDW source and IDS target systems.
Version Label	Specifies the version label of the mapping specification. For example, Beta. For more information on configuring version display of mapping specifications, refer to the Configuring Version Display topic.
Changed Description	Specifies the description of the changes made in the mapping specification. For example: A business rule for a source column was added.
Mail Com-	Specifies the mail comments which can be sent to the project users

Restoring Archived Maps As Active

Field Name	Description
ments	through an email notification. For example: Target update strategy is not updated. For more information on configuring notifications, refer to the Configuring Notifications topic.

4. Click .

The archived map is restored as a new version and the existing active map is archived.



Exporting Mapping Specifications

This section walks you through the process of exporting mapping specifications. Once the mappings are approved for coding requirements like ETL Jobs, SQL Scripts, Python Code, Spark Code, DDL Scripts, or Stored Procedures then you can export them.

You can export mapping specifications to:

- [the proprietary XML format](#)
- [generate ETL jobs](#)


Proprietary XML Format

Once the mappings are approved for coding, you can export the mappings as coding requirements in the XML format.

To export mapping specifications into proprietary XML format, follow these steps:

1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click a map.

The Mapping Specification grid appears.




The screenshot shows the 'Mapping Specification' grid in the software interface. The grid has the following columns: #, Source System Name, Source Environment Name, Source Table Name, Source Column Name, Source Column Data Type, Source Column Length, Business Rule, and Extended Business Transformation. The data rows are as follows:


#	Source System Name	Source Environment Name	Source Table Name	Source Column Name	Source Column Data Type	Source Column Length	Business Rule	Extended Business Transformation
1	erwinDIS	erwinDIS	dbo.ADS_ASSOCI	ID	bigint	8	ABS	
2	erwinDIS	erwinDIS	dbo.ADS_ASSOCI	SOURCE_OBJECT_	bigint	8	ABS	
3	erwinDIS	erwinDIS	dbo.ADS_ASSOCI	SOURCE_OBJECT_	bigint	8	ABS	

3. Click .


The Export Window page appears.



4. Select **Mapping Manager XML** and click .




5. Click .

6. Select the required mappings and click .

The following notification appears.

Proprietary XML Format



7. Click the **Download file** hyperlink.

A ZIP file is downloaded. Unzip this file to use the mapping specification in the XML format.

ETL Jobs

Once the mappings are considered 'approved for coding', you can export the mappings as coding requirements to automatically generate ETL/ELT jobs. The ETL jobs can be generated for tools, such as Informatica PowerCenter, IBM DataStage, Microsoft SQL Server SSIS, and Talend.


1. Go to **Application Menu > Data Catalog > Mapping Manager**.
2. In the **Workspace Mappings** pane, click the required map.

The **Mapping Specification** grid appears.


#	Source System Name	Source Environment Name	Source Table Name	Source Column Name	Source Column Data Type	Source Column Length	Business Rule
1	erwinDIS	erwinDIS	dbo.ADS_ASSOCI	ID	bigint	8	ABS
2	erwinDIS	erwinDIS	dbo.ADS_ASSOCI	SOURCE_OBJECT_	bigint	8	ABS
3	erwinDIS	erwinDIS	dbo.ADS_ASSOCI	SOURCE_OBJECT_	bigint	8	ABS

3. Click .

The **Export Window** page appears.




4. Click the **ETL Engineering** tab.




5. Select the required ETL tool and click .


The Multi Mapping page appears.

ETL Jobs



6. Select the mapping and click .

The following notification appears.



7. Click the **Download File** hyperlink.

The mapping specification is exported.

Creating and Managing Test Cases for Mappings

You can create test cases for testing data mappings and ETL processes in the Mapping Manager for:

- Projects
- Mappings

The test cases created at project-level apply to all the mappings created under the project. Whereas, map-level test cases apply to particular map.

Creating and managing test cases involves:

- [Creating test cases](#)
- [Adding validation steps](#)
- [Adding documents](#)
- [Managing test cases](#)

Creating Test Cases

In the Mapping Manager, you can define test cases at:

- [Project-level](#)
- [Map-level](#)


At the project-level, you can create multiple test cases. Whereas, at the map-level, you can create a single test case.

Creating Project-Level Test Cases

To create project-level test cases, follow these steps.

1. Go to **Application Menu > Data Catalog > Mapping Manager > Workspace Mappings**.
2. Expand a project and click the **Test Case** node.

The Test Case Summary page appears.



3. Click .

The Add New Test Case page appears.



Test cases created for a project are also applicable to the mappings under a project.

Creating Test Cases

4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Test Case Name	Specifies the name of the test case. For example, Verifying the Completeness of Source Metadata.
Test Case Label	Specifies the unique label for the test case. For example, Source Metadata.
Type of Testing	Specifies the type of testing. For example, Metadata Testing.
Test SQL Script	Specifies the SQL script required in the test execution. For example, select * from dbo.ADS_ASSOCIATIONS.
Description	Specifies the test objective in brief. For example: The objective of the test case is to verify the completeness of source metadata.
Expected Result	Specifies the expected result of the test case in detail. For example: The source table should have 50 columns.
Actual Result	Specifies the actual test result after the execution of the test.

Creating Test Cases

Field Name	Description
	For example: The source table has 39 columns.
Testing Comments	Specifies the testing comments about the test case. For example: The source metadata was scanned from a Sql Server database.

5. Click **Save and Exit**.

The test case is created and added to the **Test Cases** node.

Creating Map-Level Test Cases

To create map-level test cases, follow these steps.

1. Go to **Application Menu > Data Catalog > Mapping Manager > Workspace Mappings**.
2. Click a mapping and click the **Test Specification** tab.

It displays the existing project-level test cases.

The screenshot shows the 'Test Specification' tab in the Mapping Manager. On the left, a tree view shows the 'Erwin_Map (v1.04)' mapping selected. The main area displays a table of test cases with columns: #, Test Case Id, Test Case Name, Test Case Label, Type of Testing, Description, Priority, Test Case Status, Approved, and Map. One row is visible with Test Case Id '9' and Test Case Name 'T_Name'. Below the table is a 'Test Case Overview' form with fields for Test Case Id (9), External Test Case Id, Test Case Name* (T_Name), and Test Case Label. The 'Add New Test Case' button is visible in the top left of the table area.

3. Click .

The Add New Test Case page appears.

Creating Test Cases

4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Test Case Name	Specifies the name of the test case. For example, Verifying the Completeness of Source Metadata.
Test Case Label	Specifies the unique label for the test case. For example, Source Metadata.
Priority	Specifies the priority of the test case. For example, High. Priority for business rules and functional test cases can be medium or higher.
Type of Testing	Specifies the type of testing. For example, Metadata Testing.
Extendable	Specifies whether the test case is visible even when this map is archived. A map is archived whenever you create a new version of the map.
Test SQL Script	Specifies the SQL script required in the test execution. For example, select * from dbo.ADS_ASSOCIATIONS.

Creating Test Cases

Field Name	Description
Description	Specifies the test objective in brief. For example: The objective of the test case is to verify the completeness of source metadata.
Expected Result	Specifies the expected result of the test case in detail. For example: The source table should have 50 columns.
Actual Result	Specifies the actual test result after the execution of the test. For example: The source table has 39 columns.
Testing Comments	Specifies the testing comments about the test case. For example: The source metadata was scanned from a Sql Server database.
Test Case Status	Specifies the status of the test case. For example, Passed.
Approved	Specifies whether the test case is approved.

5. Click **Save and Exit**.

The test case is added under the Test Specification tab.

Once a test case is created, you can enrich it by:

- [Adding validation steps](#)
- [Adding documents](#)

[Managing test cases](#) involves:

- Updating test case status
- Approving test cases
- Exporting test cases
- Deleting test cases

Adding Validation Steps

You can add multiple validation steps to the test cases at:


- [Project-level](#)
- [Map-level](#)

You can also specify actual and expected results for each validation step.

Adding Validation Steps to Project-Level Test Cases

To add validations to project-level test cases, follow these steps.

1. In the **Workspace Mappings** pane, expand a project and click the **Test Case** node. The Test Case Summary pane appears.



2. Click .

The Add Validation Steps page appears.

Adding Validation Steps

3. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Validation Step Type	Specifies the type of validation step. For example, Data Check.
Step Name	Specifies the unique name of the step. For example, Validating Number of Columns.
Description	Specifies the description of the validation step. For example: This step validates the number of columns in the source metadata.
Expected Result	Specifies the expected result in detail. For example: The source table, dbo.ADS_ASSOCIATIONS should have 50 columns.
Actual Result	Specifies the actual test result after the execution of the test. For example: The source table contains 50 columns.
Test Step Comments	Specifies the comments about the step. For example: The source metadata was scanned from a Sql Server

Adding Validation Steps

Field Name	Description
	database.

4. Click **Save**.

The validation step is added to the test case.

Adding Validation Steps to Map-Level Test Cases

To add validations to map-level test cases, follow these steps.


1. In the **Workspace Mappings** pane, expand a project and click a mapping.
2. Click the **Test Specification** tab.
3. Double-click a map-level test case.

The Test Case Summary pane appears.

The screenshot displays the Erwin software interface. On the left, the 'Workspace Mappings' pane shows a tree view of projects and mappings, with 'Erwin_Map (v1.04)' selected. The main area is titled 'Mapping Specification' and 'Graphical Designer', with the 'Test Specification' tab active. A table lists test cases, with the second row (ID 11, Name 'Erwin_Test') selected. Below the table, the 'Test Case Overview' pane shows fields for 'Test Case Id' (11), 'Test Case Name' (Erwin_Test), 'Test Case Label', 'Priority', and 'Type of Testing'. The 'Validation Steps' tab is visible at the bottom of the overview pane. On the right, the 'Metadata Catalogue' pane shows a list of data sources and systems.

4. In the bottom pane, click the **Validation Steps** tab.
The Validation Steps tab appears.

Adding Validation Steps



5. Click .

The Add New Step page appears.

6. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Step Name	Specifies the unique name of the step.

Adding Validation Steps

Field Name	Description
	For example, Validating Number of Columns.
Validation Step Type	Specifies the type of the validation step. For example, Data Check.
Step Status	Specifies the status of the step. For example, Passed.
Description	Specifies the description about the validation step. For example: This step validates the number of columns in the source metadata.
Expected Result	Specifies the expected result in detail. For example: The source table, dbo.ADS_ASSOCIATIONS should have 50 columns.
Actual Result	Specifies the actual test result after the execution of the test. For example: The source table contains 50 columns.
Expected Result	Enter the expected result in detail, including the error-message that is displayed on screen.
Test Step Comments	Specifies the comments about the step. For example: The source metadata was scanned from a Sql Server database.

7. Click **Save**.

The validation step is added to the test case.

Adding Documents

You can add supporting documents such as text files, audio files, video files, and so on to a test case at:


- [Project-level](#)
- [Map-level](#)

Adding Documents to Project-Level Test Cases

To add documents to project-level test cases, follow these steps.

1. In the **Workspace Mappings** pane, click the **Test Cases** node of a project.

The Test Case Summary pane appears.



2. In the bottom pane, click **Document Upload** and click .


The Add Test Case Document page appears.

Adding Documents

The screenshot shows a web form titled "Add Test Case Document". It contains the following elements:

- Document Name***: A text input field with a red asterisk indicating it is mandatory.
- Document Owner**: A text input field.
- Document Object**: A text input field with a "Drag-n-Drop files here or click to select files for upload." instruction and an upload icon.
- Document Link**: A text input field.
- Intended Use Description**: A rich text editor with a toolbar containing icons for text color, background color, bold, italic, underline, bulleted list, numbered list, link, unlink, and undo.
- Approval Required Flag**: A checkbox.
- Buttons**: "Save" and "Cancel" buttons in the top right corner.

3. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Document Name	Specifies the name of the added document to the test case. For example, Source Metadata Details.
Document Object	Drag and drop document files or use  to select and upload documents.
Document Owner	Specifies the document owner's name. For example, John Doe.
Document Link	Specifies the URL of the document. For example, https://drive.google.com/file/d/1/2sC2_SZlyeFKI70On-b5YkMBq4ptA7jhg5/view
Intended Use Description	Specifies the intended use of the document. For example: The document has information about the source metadata.
Approval Required Flag	Specifies whether the document requires approval. Select the Approval Required Flag check box to select the doc-

Adding Documents

Field Name	Description
	Document status.
Document Status	Specifies the status of the document. For example, In Progress. This field is available only when the Approval Required Flag check box is selected.

4. Click **Save**.

The document is added to the test case and saved under the **Document Upload** tab.

The screenshot displays the 'Test Case Summary' interface. On the left is a 'Workspace Mappings' sidebar with a tree view. The main area shows a table of test cases. Below this, there are tabs for 'Test Case Overview', 'Validation Steps', and 'Document Upload'. The 'Document Upload' tab is active, showing a table with columns: '#', 'Document Name', 'Document Link', 'Document Status', 'Intended Use Description', and 'Options'. A single document is listed with ID '1', name 'doc1', and status 'In Progress'. A 'Self Help' button is visible on the right edge of the interface.

Once a supporting document is added, use the following options:

Preview (📄)

Use this option to preview the document.

Edit (✎)

Use this option to update the document details.

Delete (✖)

Use this option to delete the document that is not required.

Adding Documents to Map-Level Test Cases

To add documents to map-level test cases, follow these steps.

Adding Documents

1. In the **Workspace Mappings** pane, click a mapping and click the **Test Cases** node of a project.
2. Double-click a map-level test case.

The Test Overview page appears.

The screenshot shows the 'Test Overview' tab selected in the 'Test Specification' window. The 'Workspace Mappings' pane on the left shows a tree view with 'Erwin_Map (v1.04)' selected. The main area displays a table of test cases and a form for editing the selected test case.

#	Test Case Id	Test Case Name	Test Case Label	Type of Testing	Description	Priority	Test Case Status	Approved	Map
1	9	T_Name						<input type="checkbox"/>	
2	11	Erwin_Test						<input type="checkbox"/>	
3	12	New_Associatior	Association	Source to Target	Data Migrat			<input type="checkbox"/>	

Records from 1 to 3 | Page 1 | 25 rows per page

Test Case Overview | Validation Steps | Document Upload | Extended Properties

Test Case Id: 11 | External Test Case Id:

Test Case Name: Erwin_Test

Test Case Label: | Priority:

Type of Testing: | Extendable:

3. Click the **Document Upload** tab.

The screenshot shows the 'Document Upload' tab selected in the 'Test Specification' window. The 'Workspace Mappings' pane on the left remains the same. The main area displays a table for document uploads and a bottom navigation bar.

#	Document Name	Document Link	Document Status	Intended Use Description	Options
---	---------------	---------------	-----------------	--------------------------	---------

Additional Mapping Information

Map Spec Overview | Source Extract SQL | Target Update Strategy | Testing Notes | **Map Spec Docs** | Assig

4. Click .


Adding Documents

The Add Test Case Document page appears.

The screenshot shows a web form titled "Add Test Case Document". At the top right, there are "Save" and "Cancel" buttons. The form contains the following fields:

- Document Name***: A text input field.
- Document Owner**: A text input field.
- Document Object**: A large area with the text "Drag-n-Drop files here or click to select files for upload." and a blue upload icon.
- Document Link**: A text input field.
- Intended Use Description**: A rich text editor with a toolbar containing icons for text color, background color, bold, italic, underline, bulleted list, numbered list, link, unlink, and undo.
- Approval Required Flag**: A checkbox.

5. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

Field Name	Description
Document Name	Specifies the name of the physical document being attached to the test case. For example, Source Metadata Details.
Document Object	Drag and drop document files or use  to select and upload document files.
Document Owner	Specifies the document owner's name. For example, John Doe.
Document Link	Specifies the URL of the document. For example, https://drive.google.com/file/d/12sC2_SZlYeFKI70On-b5YkMBq4ptA7jhg5/view
Intended Use Description	Specifies the intended use of the document. For example: The document has information about the source metadata.

Adding Documents

Field Name	Description
Approval Required Flag	Specifies whether the document requires approval. Select the Approval Required Flag check box to select the document status.
Document Status	Specifies the status of the document. For example, In Progress. This field is available only when the Approval Required Flag check box is selected.

6. Click **Save**.

The document is added to the test case.

Once a supporting document is added, use the following options:

Preview ()

Use this option to preview the document.

Edit ()

Use this option to update the document details.

Delete ()

Use this option to delete the document that is not required.

Managing Test Cases

Managing [project-level](#) or [map-level](#) test cases involve:


- Updating test cases
- Exporting test cases
- Deleting test cases


Managing Project-Level Test Cases

To update project-level test cases, follow these steps


To update test cases, follow these steps:


1. In the **Workspace Mappings** pane, click the **Test Cases** node.



2. In the **Test Case Summary** pane, click the required test case.
3. In the **Test Case Overview** tab, click .
4. Update the necessary information.
For more information on fields, refer to [Creating Test Cases](#) topic.

Managing Test Cases


To export a test case, click the test case in the **Test Case Summary** pane, and click .

To delete a test case, click the test case in the **Test Case Summary** pane, and click .

Managing Map-Level Test Cases

To update map-level test case, follow these steps:


1. In the **Workspace Mappings** pane, click a map and click the **Test Specification** tab.



#	Test Case Id	Test Case Name	Test Case Label	Type of Testing	Description	Priority	Test Case Status	Approved
1	9	T_Name						<input type="checkbox"/>
2	11	Erwin_Test					Unspecified	<input checked="" type="checkbox"/>
3	12	New_Association	Association	Source to Target Te	Data Migration			<input type="checkbox"/>

2. Click .

The Map and Test Cases Status page appears. You can update test case status in the Test Cases Grid and Map Test Status in the bottom pane.




#	Test Case Label	Test Case Name	Test Case Status	Type of Testing	Description	Priority	Created By	Created On	Modified By	Modified On
1		Erwin_Test	Unspecified	Association	Source to Target Te Data Migration		Administrator	2019-11-11 12:52:19	Administrator	2019-11-12 17:10:14

Managing Test Cases


To approve map-level test cases, follow these steps:

1. In the **Workspace Mappings** pane, click a mapping, and click the **Test Specification** tab.




2. Click .

The Approved Test Cases page appears.



3. Select the check box against the test case under the **Approved** column.
4. Click **Save**.

To export a test case, click the test case in the **Test Case Summary** pane, and click .


To delete a test case, click the test case in the **Test Case Summary** pane, and click .

Viewing Mapping Manager Dashboard

The Mapping Manager Dashboard displays metrics that help you analyze and track your projects and mappings. It presents this information using charts and graphs.

To access Mapping Manager Dashboard, follow these steps:


1. Go to **Application Menu > Data Catalog > Mapping Manager**.



2. Click the **Mapping Manager Dashboard** pane.

The Mapping Manager Dashboard appears.

Viewing Mapping Manager Dashboard



It displays the following panes:

- **Statistics**: It displays a snapshot of statistics related to mapping projects.
- **Mapping Summary**: It displays the number of mappings in each project.
- **Mapping Status**: It displays the number of mappings in each mapping state.
- **Proactive Impact Analysis - Truncation Impacts**: It displays the number of instances of source truncation in each project.
- **Project Overview**: It displays the number of subjects, mappings, and assigned users in each project.
- **Mapping Classification**: It displays the number of active, archived, and published mappings in each project.
- **Mapping Assignments**: It displays the number of designers, approvers, developers, and testers assigned to mappings
- **Sources/Targets Not Mapped**: It displays the number of sources and targets not mapped in each project.
- **Test Case Status**: It displays the number of test cases under a test case status.
- **Project Test Cases**: It displays the number of test cases in each project.
- **User Test Cases**: It displays the number of test cases created by each user.

Statistics

The Statistics pane displays the total number of projects, subjects, mappings, source tables, target tables, possible truncations, and users. For example, in the following image there are sixteen projects, eighty-six mappings, forty-four source tables, forty-six target tables, eighty-four possible truncations, and four users.




You can click the hyperlink to view further details. For example, if you click the hyperlink for the Target Tables. The Target Table Details page appears.

Target Tables Details			
#	Table Name	Environment Name	System Name
1	Account	erwinSales	SQLTechPubs
2	Account	Presentation Layer	TABLEAU
3	Account	Presentation Layer	TABLEAU
4	Account	PRESENTATION LAYER	TABLEUAU
5	Account	TechPubs	PRESENTATION LAYER
6	Account	TechPubs	Salesforce
7	APPQOSSYS.WLM_CLASSIFIER_PLAN	TechPubs	Oracle
8	APPQOSSYS.WLM_CLASSIFIER_PLAN	TechPubs	Oracle

Mapping Summary


The Mapping Summary pane displays the number of mappings in each project in a pie chart. To open the chart in the Dashboard View, click the pie-chart.

Viewing Mapping Manager Dashboard



Each slice of the pie chart corresponds to a project. You can drill down and view detailed information in the list format. To view detailed information about mappings in a project, click a slice. The Details View tab opens. It displays project name, subject name, map name, and map version.

Viewing Mapping Manager Dashboard



The screenshot shows a web application window titled "Mapping Summary". It has two tabs: "Dashboard View" and "Details View", with "Details View" selected. Below the tabs is a table with four columns: "#", "Project Name", "Subject Name", "Map Name", and "Map Version". The table contains 12 rows of data, all with "Lineage Demo" in the Project Name column. The Map Name column contains various names like "Informatica_m_CBDR_BDM_CASA", "Talend_staging", "test", "TestDataMap1", "TestMap2", "TestMap3", "Tech Pubs", "Create a New Map", "how", "Account Tableau Report", "Line Mapping", and "map_map". The Map Version column shows values of 1.00 or 1.02.


#	Project Name	Subject Name	Map Name	Map Version
1	Lineage Demo		Informatica_m_CBDR_BDM_CASA	1.00
2	Lineage Demo		Talend_staging	1.00
3	Lineage Demo		test	1.00
4	Lineage Demo		TestDataMap1	1.00
5	Lineage Demo		TestMap2	1.00
6	Lineage Demo		TestMap3	1.00
7	Lineage Demo		Tech Pubs	1.00
8	Lineage Demo		Create a New Map	1.00
9	Lineage Demo		how	1.00
10	Lineage Demo		Account Tableau Report	1.02
11	Lineage Demo		Line Mapping	1.00
12	Lineage Demo		map_map	1.00

Mapping Status

The Mapping Status pane displays the number of mappings under each mapping state in a pie chart. By default there are two mapping states, In Progress and Approved. You can create your own mapping states depending on your requirements. For more information on creating mapping states, refer to the [Configuring Mapping State Settings](#) topic.


To open the chart in the Dashboard View, click the pie chart.

Viewing Mapping Manager Dashboard



Each slice corresponds to a mapping state. You can drill down and view detailed information in the list format. To view detailed information about maps in a mapping state, click a slice of the pie-chart.

Viewing Mapping Manager Dashboard




#	Project Name	Subject Name	Map Name	Map Version	State Name
	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
1	erwinDIS		Data Integration	1.00	Approved
2	erwinDIS		SalesforceIntegratic	1.00	Approved
3	erwinDIS		BugTrial	1.00	Approved
4	erwinDIS		erwinSalesIntegratic	1.01	Approved

Proactive Impact Analysis - Truncation Impacts

The Proactive Impact Analysis - Truncation Impacts pane displays the number of instances where the target column length is smaller than the source column length in each project in a pie-chart. To open the chart in the Dashboard View, click the pie chart.

Viewing Mapping Manager Dashboard




Each slice of the pie chart corresponds to a project. You can drill down and view detailed information in the list format.

To view detailed information about truncated sources in a project, click a slice of the pie chart. The Details View tab opens. It displays project name, subject name, map name, source and target column names.

#	Project Name	Subject Name	Map Name	Source Table Name	Target Table Name	Source Column Name	Target Column Name	Source Column Length	Source Column Precision	Target Column Length	Target Column Precision	Map Version
1	Test Source		mo_STGTPCH_SF10000	TPCH_SF10000.LINEITEM	stg.STG_LINEITEM	L_LINENUMBER	LINEITEM_HSH	38		16		1.00
2	Test Source		mo_STGTPCH_SF10000	TPCH_SF10000.LINEITEM	stg.STG_LINEITEM	L_LINENUMBER	LINEITEM_HSH_DIFF	38		16		1.00
3	Test Source		mo_STGTPCH_SF10000	TPCH_SF10000.LINEITEM	stg.STG_LINEITEM	L_ORDERKEY	TPCH_SF10000.ORDER	38		16		1.00
4	Test Source		mo_STGTPCH_SF10000	TPCH_SF10000.LINEITEM	stg.STG_LINEITEM	L_PARTKEY	TPCH_SF10000.PART_H	38		16		1.00


Project Overview

The Project Overview pane displays the number of subjects, mappings, and assigned users in each project in a bar graph. To open bar graph in the Dashboard View, click the bar graph.



Each set of three bars corresponds to a project. You can view detailed information in the list format. To view the Detailed information about mappings, subjects, or assigned users of a project click the corresponding bar. For example, if you click the mappings bar then the Mappings tab opens.

Viewing Mapping Manager Dashboard



#	Project Name	Subject Name	Map Name	Map Version
1	erwinDIS		Data Integration	1.00
2	erwinDIS		SalesforceIntegration	1.00
3	erwinDIS		BugTrial	1.00
4	erwinDIS		TechPubsBUGTrial	1.00
5	erwinDIS		erwinSalesIntegration	1.01


To view a list of subjects, click the **Subjects** tab.

To view a list of the assigned users, click the **Assigned Users** tab.

Mapping Classification

The Mapping Classification pane displays the number of active, archived, and published mappings in each project in a bar graph. To open the bar graph in the Dashboard View, click the bar graph.

Viewing Mapping Manager Dashboard




Each set of three bars corresponds to a project. You can drill down and view detailed information. To view detailed information about status of mappings in a project, click a bar. The Details View tab opens. It displays project name, subject name, map name, map version, and status.

#	Project Name	Subject Name	Map Name	Map Version	Status	Map Published
1	erwinDIS		BugTital	1.00	Active	
2	erwinDIS		Data Integration	1.00	Active	
3	erwinDIS		erwinSalesIntegration	1.00	Passive	✓
4	erwinDIS		erwinSalesIntegration	1.01	Active	
5	erwinDIS		SalesforceIntegration	1.00	Active	
6	erwinDIS		TechPubsBUgTital	1.00	Active	

Mapping Assignments

The Mapping Assignments pane displays the number of designers, approvers, developers, and testers assigned to mappings in each project in a bar graph. For more information on mapping assignments, refer to the [Assigning Mapping Specifications to Users](#) topic.

To open the bar graph in the Dashboard View, click the bar graph.



Each set of three bars corresponds to a project. You can drill down and view detailed information in the list format. To view detailed information about mapping assignments in a pro-

Viewing Mapping Manager Dashboard


ject, click a bar. The Detail View tab opens. It displays project name, subject name, map name, assigned user's full name, and assignment status.

Dashboard View		Details View						
#	Project Name	Subject Name	Map Name	Map Description	Assignee Full Name	Responsibility	Assignment Status	Last Modified By
	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
1	erwinDIS		Data Integr		Administrat	Mapping D	In Progress	Administrator
2	erwinDIS		SalesforceL		Administrat	Mapping D	In Progress	Administrator
3	erwinDIS		BugTrial	Testing for c	Saras Ojha	Mapping A	Not Startec	Administrator
4	erwinDIS		BugTrial	Testing for c	Administrat	Mapping D	In Progress	Administrator
5	erwinDIS		BugTrial	Testing for c	Jane Doe	Mapping E	Not Startec	Administrator
6	erwinDIS		BugTrial	Testing for c	public - De	Mapping Tr	Not Startec	Administrator
7	erwinDIS		TechPubsBl	TechPubsBl	Administrat	Mapping D	In Progress	Administrator
8	erwinDIS		erwinSalesL		Administrat	Mapping D	In Progress	Administrator

Sources/Targets Not Mapped

The Sources/Targets Not Mapped pane displays the number of sources and targets not mapped in each project in a bar graph. To open the bar graph in the Dashboard View, click the bar graph.

Viewing Mapping Manager Dashboard



Each set of two bars corresponds to a project. You can drill down and view detailed information in the list format. To view the detailed information about sources and target not mapped in a project, click a bar. The Details View tab opens. It displays project name, map name, and target and source details.


Viewing Mapping Manager Dashboard

Dashboard View		Details View					
Targets Not Mapped		Sources Not Mapped					
#	Project Name	Subject Name	Map Name	Target System Name	Target Environment Name	Target Table Name	Target Column Name
	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
1	Lineage Demo		Account Tableau	Snowflake	Snowflake_STG	stg.STG_LINEITEM	SQN_NUM
2	Lineage Demo		Account Tableau	Snowflake	Snowflake_STG	stg.STG_LINEITEM	LOAD_DTS
3	Lineage Demo		Account Tableau	Snowflake	Snowflake_STG	stg.STG_LINEITEM	REC_SRC
4	Lineage Demo		Account Tableau	Snowflake	Snowflake_STG	stg.STG_LINEITEM	MLTID
5	Lineage Demo		Account Tableau	Snowflake	Snowflake_STG	stg.STG_LINEITEM	BKCC
6	Lineage Demo		Account Tableau	Snowflake	Snowflake_STG	stg.STG_LINEITEM	BWSC
7	Lineage Demo		Account Tableau	Snowflake	Snowflake_STG	stg.STG_LINEITEM	SQN_NUM
8	Lineage Demo		Account Tableau	Snowflake	Snowflake_STG	stg.STG_LINEITEM	LOAD_DTS
9	Lineage Demo		Account Tableau	Snowflake	Snowflake_STG	stg.STG_LINEITEM	REC_SRC
10	Lineage Demo		Account Tableau	Snowflake	Snowflake_STG	stg.STG_LINEITEM	MLTID
11	Lineage Demo		Account Tableau	Snowflake	Snowflake_STG	stg.STG_LINEITEM	BKCC
12	Lineage Demo		Account Tableau	Snowflake	Snowflake_STG	stg.STG_LINEITEM	BWSC
13	Lineage Demo		map.map(1.00)	erwin DM	DM Landing	Citizens	CitizenID

Test Case Status

The Test Case Status pane displays the number of test cases under a test case status in a pie chart. To open the chart in the Dashboard View, click the pie chart.

Viewing Mapping Manager Dashboard




Each slice of the pie chart corresponds to a test case status. You can drill down and view detailed information in the list format. To open the detailed information about test cases, click a slice. The Details View tab opens. It displays project name, map name, and test case names.

Dashboard View		Details View				
#	Project Name	Subject Name	Map Name	Test Case Id	Test Case Name	Test Case Label
	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
1	Lineage Demo			3	ETL Testing	Alpha
2	Lineage Demo		Account Tablea	4	Account_Tak	
3	erwinDIS			1	Validating sc	Alpha

Project Test Cases

The Project Test Cases pane displays the number of test cases in each project in a pie-chart. To open the chart in the Dashboard View, click the pie chart.




Each slice in the pie chart corresponds to a project. You can drill down and view detailed information in the list format.

To view the detailed information about test cases in a project, click a slice of the pie chart. The Details View tab opens. It displays project name, subject name, map name, test case ID, test case name, and test case label.

#	Project Name	Subject Name	Map Name	Test Case Id	Test Case Name	Test Case Label
1	erwinDS			1	Validating sour	Alpha
2	erwinDS		Data Integration	2	Customer-Acc	Alpha

User Test Cases

The User Test Cases pane displays the number of test cases created by each user in a pie chart. To open the chart in the Dashboard View, click the pie chart.



Each slice of the pie chart corresponds to a user. You can drill down to view detailed information in the list format.

To view the detailed information about test cases created by a user, click a slice of the pie chart. The Details View tab opens. It displays project name, subject name, map name, test case ID, test case name, and test case label.

#	Project Name	Subject Name	Map Name	Test Case Id	Test Case Name	Test Case Label
1	Lineage Demo			3	ETL Testing	Alpha
2	erwinDIS			1	Validating sour	Alpha
3	erwinDIS		Data Integration	2	Customer-Acc	Alpha