

erwin Data Modeler

**DM Connect for DI** 

Release 15.0

## **Legal Notices**

This Documentation, which includes embedded help systems and electronically distributed materials (hereinafter referred to as the "Documentation"), is for your informational purposes only and is subject to change or withdrawal by Quest Software, Inc and/or its affiliates at any time. This Documentation is proprietary information of Quest Software, Inc and/or its affiliates and may not be copied, transferred, reproduced, disclosed, modified or duplicated, in whole or in part, without the prior written consent of Quest Software, Inc and/or its affiliates

If you are a licensed user of the software product(s) addressed in the Documentation, you may print or otherwise make available a reasonable number of copies of the Documentation for internal use by you and your employees in connection with that software, provided that all Quest Software, Inc and/or its affiliates copyright notices and legends are affixed to each reproduced copy.

The right to print or otherwise make available copies of the Documentation is limited to the period during which the applicable license for such software remains in full force and effect. Should the license terminate for any reason, it is your responsibility to certify in writing to Quest Software, Inc and/or its affiliates that all copies and partial copies of the Documentation have been returned to Quest Software, Inc and/or its affiliates or destroyed.

TO THE EXTENT PERMITTED BY APPLICABLE LAW, QUEST SOFTWARE, INC. PROVIDES THIS DOCUMENTATION "AS IS" WITHOUT WARRANTY OF ANY KIND, INCLUDING WITHOUT LIMITATION, ANY IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NONINFRINGEMENT. IN NO EVENT WILL QUEST SOFTWARE, INC. BE LIABLE TO YOU OR ANY THIRD PARTY FOR ANY LOSS OR DAMAGE, DIRECT OR INDIRECT, FROM THE USE OF THIS DOCUMENTATION, INCLUDING WITHOUT LIMITATION, LOST PROFITS, LOST INVESTMENT, BUSINESS INTERRUPTION, GOODWILL, OR LOST DATA, EVEN IF QUEST SOFTWARE, INC. IS EXPRESSLY ADVISED IN ADVANCE OF THE POSSIBILITY OF SUCH LOSS OR DAMAGE.

The use of any software product referenced in the Documentation is governed by the applicable license agreement and such license agreement is not modified in any way by the terms of this notice.

The manufacturer of this Documentation is Quest Software, Inc and/or its affiliates.

Provided with "Restricted Rights." Use, duplication or disclosure by the United States Government is subject to the restrictions set forth in FAR Sections 12.212, 52.227-14, and 52.227-19(c) (1) - (2) and DFARS Section 252.227-7014(b)(3), as applicable, or their successors.

Copyright © 2025 Quest Software, Inc and/or its affiliates All rights reserved. All trademarks, trade names, service marks, and logos referenced herein belong to their respective companies.

## **Contact erwin**

#### Understanding your Support

Review support maintenance programs and offerings.

#### Registering for Support

Access the **erwin support** site and register for product support.

#### Accessing Technical Support

For your convenience, erwin provides easy access to "One Stop" support for all editions of **erwin Data Modeler**, and includes the following:

- Online and telephone contact information for technical assistance and customer services
- Information about user communities and forums
- Product and documentation downloads
- erwin Support policies and guidelines
- Other helpful resources appropriate for your product

For information about other erwin products, visit erwin by Quest Products page.

#### Provide Feedback

If you have comments or questions, or feedback about erwin product documentation, you can send a message to **techpubs@erwin.com**.

#### **News and Events**

Visit News and Events to get up-to-date news, announcements, and events. View video demos and read up on customer success stories and articles by industry experts.

# **Contents**

DM Connect for DI Overview	6
Workflow	6
Prerequisites	9
erwin Mart Portal System Requirements	9
erwin DI System Requirements	15
Database Server Specifications	16
Permissions	17
Minimum erwin Mart Permissions	17
Minimum erwin DI Permissions	17
erwin DI DocumentsPath	18
Configuration	20
Scenario: Schedule Jobs to Export Data Models to erwin DI	23
Case I: Run Job	31
Case II: Modify Job	31
Case III: Recurring Job-No Change in Models	31
Case IV: New Model in the Folder	32
Scenario: Schedule Jobs to Import Data Models from erwin DI to erwin DN	133
Scenario: Export Logical Names from erwin DM to erwin DI	40
Scenario: Import Source and Target Data into Mapping Manager	45
Scenario: NSM Files	47
Case I: One NSM File, Multiple Models	48
Case II: Multiple NSM Files, Multiple Models	48
Scenario: View Logs	49

Reference: Data Sharing between erwin DM and erwin DI	50
Limitations	.53

## **DM Connect for DI Overview**

erwin now offers an integration, DM Connect for DI, between two powerful products, erwin Data Modeler erwin DM) and erwin Data Intelligence (erwin DI). This offering enables you to maintain a single metadata and glossary source across erwin DM and erwin DI using erwin Mart Portal as an interface. Apart from this, DM Connect for DI offers the following benefits:

- Use data models as a foundation for data governance initiatives
- · Automatically update data catalog
- Maintain a business glossary based on logical names and naming standards


### Workflow

erwin DM supports several target databases. It provides a powerful and robust workspace to create rich data models based on these target databases. Further, it provides connectivity to erwin Mart Portal; where you can store your rich data models in a mart repository.

erwin Mart Portal acts an interface between erwin DM and erwin DI. It enables you to schedule jobs to export data models and data sources from your mart repository to erwin DI Data Catalog and vice versa. Further, it integrates the naming standards set up on your models into the Business Glossary Manager.

erwin DI enables you to use your data models as a foundation for your data governance initiatives. It enables you to maintain a semantic lineage between metadata and business objects.

To summarize, erwin Data Modeler, erwin Mart Portal, and erwin DI work together as follows.



The following table explains the erwin DM, erwin Mart Portal, erwin DI version compatibility:

Products-Versions	erwin DI 12.1	erwin DI 13.0	erwin DI 14.0	erwin DI 15.0	erwin DI 15.0.1
erwin Mart Portal 2021R1	No	No	No	No	No
erwin Mart Portal 12.0	No	No	No	No	No
erwin Mart Portal 12.1	Yes	Yes	No	No	No

#### **DM Connect for DI Overview**

Products-Versions	erwin DI				
F10000013-VE1310113	12.1	13.0	14.0	15.0	15.0.1
erwin Mart Portal 12.5	No	Yes	Yes	No	No
erwin Mart Portal 12.5.1	No	Yes	No	No	No
erwin Mart Portal 12.5.2	No	Yes	Yes	No	No
erwin Mart Portal 14.0	No	No	Yes	No	No
erwin Mart Portal 14.1	No	No	No	Yes	No
erwin Mart Portal 15.0	No	No	No	No	Yes

Before configuring erwin DM Connect for , ensure that the prerequisites for erwin Mart Portal and erwin Data Intelligent (erwin DI) are in place:

- System requirements:
  - erwin Mart Portal
  - erwin DI
  - Permissions:
    - erwin Mart Portal
    - erwin DI
- erwin DI DocumentsPath

## erwin Mart Portal System Requirements

Refer to the following tables for minimum system requirements:

Parameter	Requirement	Additional Inform- ation
Hard- ware/Work- station	<ul> <li>VM or Dedicated Physical Server</li> <li>Windows-based workstation</li> <li>100 GB of disk space or more as required to support your specific mart</li> <li>Processor - 64-bit, minimum 4 cores</li> <li>RAM:         <ul> <li>Only erwin Mart Portal: 16 GB</li> <li>Both erwin Mart Portal and erwin ER360: 32 GB</li> </ul> </li> </ul>	
Operating System	<ul> <li>Microsoft Windows Server 2016</li> <li>Microsoft Windows Server 2019</li> <li>Microsoft Windows Server 2022</li> <li>All current Microsoft Windows critical updates</li> </ul>	
Database	<ul> <li>Microsoft SQL Server 2017, 2019, and 2022. You can also use Microsoft SQL Azure and Amazon RDS SQL Server.</li> <li>Oracle 18c, 19c, 21c, and Oracle Cloud</li> </ul>	• The Mart Portal can use a stan-

Parameter	Requirement	Additional Inform- ation
	<ul> <li>PostgreSQL 12.x, 13.x, 14.x, 15.x, 16.x, and 17.x. You can also use PostgreSQL for Amazon RDS.</li> <li>For DM Connect for DI, the minimum SQL Server version requirement is SQL Server 2016 SP2</li> </ul>	dalone or share an existing database server for a Microsoft SQL Server.  The SQL Server 2017, 2019, and 2022 TRUSTWORTHY database property is no longer required for the mart. After you install this product, you can optionally reset this property to OFF.  The database user account that is used to configure the Mart must have the dba_owner role assigned.  (Optional) To use the Korean language, use the Korean_wansung_Cl_AS character set. Select the character set while creating the Mart database (in the Collation field). For more information, see the

Parameter	Requirement	Additional Inform- ation
		SQL Server documentation.
		Oracle:
		<ul> <li>The Mart Portal can use a standalone or can share an existing database server for an Oracle database. You can also use a pluggable database.</li> <li>To create the Mart, you must be the database schema owner user and you must have the DBA role in the target database on the Oracle server. The DBA role is required for the user who is specified in the Configure Mart Portal dialog. If the DBA privilege of this user is revoked, then erwin DM users will not be able to save</li> </ul>
		model changes

Parameter	Requirement	Additional Inform- ation
		to the Mart.  • (Optional) You have modified the following parameters in the initialization file (InitSID.ora):
		Remote_OS_ Authent=T
		OS_Authent_ Prefix=TRUE
		<ul> <li>(Optional) To use the Korean language with the Mart database, use KO16MSWIN9-49 or AL32UTF8 character set depending on your operating system language pack. For more information, see the Oracle documentation.</li> <li>If the Mart database is an Oracle database, the default tablespaces that were used for initializing any earlier</li> </ul>

Parameter	Requirement	Additional Inform- ation
		release of r9 series Mart are available for the latest release.
		PostgreSQL:
		<ul> <li>The Mart Portal can use a standalone or can share an existing database server for PostgreSQL.</li> <li>The database user account that is used to configure the Mart must have super user permissions.</li> </ul>
erwin Mart Portal Web Cli- ent - Browser	<ul> <li>Latest versions of the following browsers:</li> <li>Microsoft Edge</li> <li>Mozilla Firefox</li> <li>Google Chrome</li> <li>Apple Safari</li> </ul>	
Web Client Workstation	<ul> <li>Processor - i3 or higher</li> <li>RAM - 8 - 16 GB</li> <li>Minimum Free Space - 8 - 16 GB</li> </ul>	
Web Server	Apache Server 2.4.63	
JDK	21.0.7	
MartPortal Service	In the C:\Program Files\erwin\Mart Portal\create_service.cmd, update the RAM size setting to increase the RAM in MBs:  reg add "HKLM\SYSTEM\CurrentControlSet\Services\erwinMartPortal\Parameters" /v	The required RAM size ranges from 2 to 10 GB for all services.

rerequisites		
Parameter	Requirement	Additional Inform- ation
	Application /d "\"%JRE_HOME%\bin\java.exe\" - Xms2048m -Xmx10240m -Dlog-ging.config=\"file:C:\Program Files\erwin\Mart Portal\MartApp\config\log4j2-portal.xml\" -jar \"C:\Program Files\erwin\Mart Portal.jar\"" /f	
ER360 Service	In the C:\Program Files\erwin\Mart Portal\create_service.cmd, update the RAM size setting to increase the RAM in MBs:  reg add "HKLM\SYSTEM\CurrentControlSet\Services\erwinER360\Parameters" /v Application /d "\"%JRE_HOME%\bin\java.exe\" - Xms2048m -Xmx10240m -Dlog-ging.config=\"file:C:\Program Files\erwin\Mart Portal\MartApp\config\log4j2-er360.xml\" -jar \"C:\Program Files\erwin\Mart Portal\MartApp\ER360.jar\"" /f	
Vault Service	In the C:\Program Files\erwin\Mart Portal\create_service.cmd, update the RAM size setting to increase the RAM in MBs:  reg add "HKLM\SYSTEM\CurrentControlSet\Services\erwinVaultService\Parameters" /v Application /d "\"%JRE_HOME%\bin\java.exe\" - Xms2048m - Xmx10240m -Dlog-ging.config=\"file:C:\Program Files\erwin\Mart Portal\MartApp\config\log4j2-vaultservice.xml\" -jar \"C:\Program Files\erwin\Mart Portal\MartAp-p\vaultservice.jar\"" /f	
Job Scheduler Service	In the C:\Program Files\erwin\Mart Portal\create_service.cmd, update the RAM size setting to increase the RAM in MBs:  reg add "HKLM\SYSTEM\CurrentControlSet\Services\erwinMartJobSchedulerService\Parameters" /v Application /d "\"%JRE_HOME%\bin\java.exe\" - Xms2048m - Xmx10240m -Dlog-	

Parameter	Requirement	Additional Inform- ation
	ging.config=\"file:C:\Program Files\erwin\Mart Portal\MartApp\config\log4j2-mart- jobschedulerservice.xml\" -jar \"C:\Program Files\er- win\Mart Portal\MartApp\MartJobScheduler.jar\"" /f	
	In the C:\Program Files\erwin\Mart Portal\create_ service.cmd, update the RAM size setting to increase the RAM in MBs:	
Search Service	reg add "HKLM\SYSTEM\CurrentCon- trolSet\Services\erwinSearchService\Parameters" /v Application /d "\"%JRE_HOME%\bin\java.exe\" - Xms2048m - Xmx10240m -Dlog- ging.config=\"file:C:\Program Files\erwin\Mart Portal\MartApp\config\log4j2-searchservice.xml\" -jar \"C:\Program Files\erwin\Mart Portal\MartApp\search-ser- vice.jar\"" /f	
Cache Service	In the C:\Program Files\erwin\Mart Portal\create_service.cmd, update the RAM size setting to increase the RAM in MBs:  reg add "HKLM\SYSTEM\CurrentControlSet\Services\erwinCacheService\Parameters" /v Application /d "\"%JRE_HOME%\bin\java.exe\" - Xms2048m - Xmx10240m -Dlog-ging.config=\"file:C:\Program Files\erwin\Mart Portal\MartApp\config\log4j2-cacheservice.xml\" -jar \"C:\Program Files\erwin\Mart Portal\MartApp\cache-service.jar\"" /f	

Ensure that you always install erwin Mart Portal on Windows operating system.

# erwin DI System Requirements

Parameter	Requirement
Hardware/Workstation	VM or Dedicated Physical Server

Parameter	Requirement	
	<ul> <li>Processor - 64-bit, minimum 4 cores</li> <li>RAM: <ul> <li>16 GB for limited user POCs</li> <li>32-64 GB for enterprise production deployment</li> </ul> </li> <li>Hard Disk Drive - 200-300 GB</li> </ul>	
Operating System	<ul> <li>Microsoft Windows - Windows Server 2016 and above</li> <li>Linux v4.19 and above</li> <li>RHEL 8.0 and 8.5</li> <li>Amazon Linux 2</li> </ul>	
	• SQL Server 2016, 2017, 2019	
Database	For DM Connect for DI, the minimum SQL Server version requirement is SQL Server 2016 SP2	
	Oracle 12c, 18c, 19c	
Browser	<ul> <li>Microsoft Edge v86x or newer</li> <li>Google Chrome v86.0 or higher</li> <li>Mozilla Firefox v82.0 or higher</li> </ul>	
Web Servers	Apache Tomcat v9.0.58	
Web Server Memory Allocation	Allot at least 50 percent of available memory.	
	For example, if available memory is 16GB, allot at least 8GB.	
Web Client Workstation	<ul> <li>Processor - i3 or higher</li> <li>RAM - 8GB minimum</li> <li>Minimum Free Space - 1-2GB</li> </ul>	

In case of enterprise deployment, for the best performance, it is recommended to allot at least 0.5 GB space per user on the application server. For example, if 30 users log on simultaneously, the application server must have at least 15 GB of RAM allocated to it.

The above RAM allocation does not indicate the RAM of the server machine. It indicates the physical RAM allocation to the application server.

## **Database Server Specifications**

The following table lists database server specifications:

Parameter	Requirement
Server Type	Dedicated standalone server
Processor	64-bit, minimum 4-8 cores
RAM	32 GB
Hard Disk Drive	250-500 GB
Tablespace	50 GB, minimum

erwin DI requires a dedicated schema/database (SQL Server or Oracle) with at least 50 GB tablespace allocated to it, which increases exponentially based on usage.

#### **Permissions**

To use DM Connect for DI, you need certain permissions on erwin Mart Portal and erwin Data Intelligence (DI).

### **Minimum erwin Mart Permissions**

You can use DM Connect for DI only if your account has been assigned the following profiles:

- Administrator
- Architect

### Minimum erwin DI Permissions

Metadata Manager	
Create System	
Systems/System Tabs/View System Details	
List Systems	
Systems/Add Environment	
Systems/List Environments	
Systems/System Environments/Import Environment	

#### Metadata Manager

Systems/System Environments/New Version

Systems/System Tabs/View Environment Details

Systems/Configure Expanded Logical Name

Systems/System Environments/Environment Tabs/Extended Properties/Edit Extended Properties

Systems/System Environments/Scan Metadata

Systems/System Environments/Environment Tabs/EnvironmentDetails

#### **Mapping Manager**

Projects/Create Project

Projects/Mappings/Create Mapping

Projects/Project Tabs/Project Details/View Project Details

Projects/Mappings/Mapping Grid/Edit Mapping Specification Grid (Any one permission in child permissions)

#### **Business Glossary Manager**

Custom Objects/Catalog/Create

Custom Objects/Catalog/Edit

Custom Objects/Catalog/View

Custom Objects/Catalog/Custom Objects/Create

Custom Objects/Catalog/Custom Objects/Edit

Custom Objects/Catalog/Custom Objects/View

Custom Objects/Import Catalog

### erwin DI DocumentsPath

To be able to export or import data between erwin DM and erwin DI, ensure that you update the iccdocuments.properties file in erwin DI as follows:

#### Windows:

When you install erwin DI on a Windows machine, the correct document path is configured automatically to a default location. If the default installation location changes, ensure you follow these steps.

If you change the default installation location, follow these steps:

- 1. Open the **iccdocuments.properties** file from the following location: Apache Software Foundation\Tomcat 8.5\webapps\<Application Name>\WEB-INF\configuration\properties\iccdocuments.properties
- 2. Change the **DocumentsPath** value to the current installation location: <drivename>:/<application name>

For example, consider you changed the installation location from the default location to:D:\Apache Software Foundation\Tomcat 8.5\webapps\erwinDISuite\WEB-INF\configuration\properties.Then, change the **DocumentsPath** to:D:/erwinDISuite

#### Linux:

Ensure that you follow these steps:

- 1. Open the **iccdocuments.properties** file from the following location: /opt/tomcat/webapps/<<erwinDISuite>>/WEB-INF/configuration/properties/iccdocuments.properties
- 2. Change the **DocumentsPath** value to: opt/tomcat/<application name>


For example, change the **DocumentsPath** from *C:/MappingManager* to: opt/tomcat/erwinDISuite

## Configuration

To import and export data models, data sources, and naming standards using DM Connect for DI, you need to configure your erwin Data Intelligence (erwin DI) application in erwin Mart Portal.


To configure erwin DI, follow these steps:

1. Go to Application Menu > Settings > DI Configurations. The DI Configurations page appears.



2. Click Add Configuration.

The Add New Configuration section appears.



3. Configure your erwin DI connection parameters as follows:

Field	Description	
Configuration Name	Specify a unique name for the configuration	
Server Name	Specify the server address, where erwin DI is installed	
Application Name	Specify the name of your erwin DI Application	
Port	Specify the port on your server that is used for erwin DI	

### Configuration

Field	Description	
Enable SSL	Specify whether you want to connect to the server through a secured connection	
Username	Specify your erwin DI user name	
Password	Specify your erwin DI password	
Session Timeout	Specify erwin DI's session time out duration in minutes	

#### 4. Click **Test**.

#### 5. Click Save.

Your connection is tested and saved. You can set up multiple erwin DI configurations and use them as required.

An Export to DI job converts a model to erwin DI compatible format and then,

- exports the model to the Metadata Manager
- exports the source and target column data from a dimensional model into the Mapping Manager

Once source and target column data is exported, any updates made to them are not exported when the job runs again.


If the model has an associated NSM file, it exports the file to the Business Glossary Man-

For more information about data sharing between erwin Data Modeler (erwin DM) and erwin Data Intelligence(erwin DI), refer to the Data Sharing topic.

By default the DM Connect for DI app opens in the Calendar view. You can toggle the page view between the List View ( ) or Calendar View ( ) using the respective buttons on the page toolbar.


To schedule jobs, follow these steps:

1. In the header pane, click and then click **DM Connect for DI**. The DM Connect for DI page opens.



2. Click Export Job.

The Add Export Job page appears.



#### 3. Set up job parameters as follows:

Tab	Field	Description
		Select models from mart catalog to export.
Catalogs	Catalog Tree	Before you select models, you can use the All Catalogs or Loaded Catalogs to display all available catalogs or only the expanded catalogs respectively.  Apart from that, after you select catalogs, you can click to view only the selected catalogs in the Catalogs section.
	Include NSM	Select whether naming standards must be exported. A catalog named by the NSM file is created under Business Glossary Manager > DM NSM Files cus-

Tab	Field	Description
	tom asset.	
		Ensure that the DM NSM Files asset is available in the Business Glossary Manager.

Tab	Field	Description
DI Information	Connectors	Select a configuration to use for the export job.

Tab	Field	Description
	Systems Name	Enter a system name. This corresponds to System in Metadata Manager.
	Environment Name	Use the predefined macros to set the environment name. This corresponds to Environment in Metadata manager.
		For system and environment names, following special characters are allowed:  • System: - (hyphen), _ (underscore), and space  • Environment: @ (at sign), \$ (dollar sign), & (ampersand), / (slash mark), - (hyphen), _ (underscore), and space  All other special characters are replaced with _ (underscore).
	Export Option	Select a suitable export option:
		Add New:
		<ul> <li>If an environment exists, this option adds any new tables or columns to it.</li> </ul>
		<ul> <li>If an environment does not exist, this option creates an environment and adds tables and columns to it.</li> </ul>
		Update Existing + Add New:
		<ul> <li>If the existing model objects have changed, this option exports the updates to the existing model objects in erwin DI.</li> </ul>
		<ul> <li>Also, it exports any new objects in the model to erwin DI.</li> </ul>
		Update Existing + Add New + Invalidate:


Tab	Field	Description
		Along with the functionality of Update Existing + Add New option, this option invalidates any deleted tables or columns.  • Delete & Reload: This option deletes all the tables and columns. Then, it exports them again.
	Version	Select whether a version of an existing environment must be created. This archives the existing environment.

Tab	Field	Description
	Job Name	Specify a job name.
	Start Date/Time	Select the date and time at which the job must start.
	Job Interval	Select a suitable frequency at which the job must run. You can set the job to run once or recur daily, weekly, monthly, or yearly. You can also set up custom recurrence for jobs.
	Frequency	Select the hourly frequency at which the job should run.
		This property is available only when you set the Job Interval to Recurring.
	End Date/Time	If you set up recurring jobs, select the date and time at which the recurrence must end.
Job Information	Days	Select the days of the week on which the job should run. The days available here depend on the End Date/Time.
		This property is available only when you set the Job Interval to Recurring.
	Notify Me	Select the check box to receive a notification when the job status changes. This enables the Notification Email and CC List fields.
	Notification Email	Specify the email address at which you want to receive the notification.
	CC List	Specify a semi-colon-separated list of email addresses that must receive the job notification.
	Run Now	Select the check box to run the job immediately.


### 4. Click Save.

The job is added to the calendar with its **Job State** set to Scheduled.


The job runs according to the schedule and exports data model to Metadata Manager and naming standards to Business Glossary Manager.



Database connection parameters such as DBMS Name/DSN, IP Address/Host Name, Port, and Business Entity Type (System Environment Type) are stored in environment details.



Also, the UDPs and validation rules in the model are exported to the Extended Properties tab in Metadata Manager.



## Case I: Run Job

The Run Job option immediately runs a job. This option works only if the selected job is a recurring job in the scheduled state.

## Case II: Modify Job

The Manage Job option lets you modify an existing scheduled job. If you modify a job:

- before its run schedule, the changes take effect when the job runs
- while it is running, the job is cancelled, and changes are saved. They take effect when the job runs next time.
- after it is past its schedule, the job runs according to the new schedule

## Case III: Recurring Job-No Change in Models

Recurring jobs run based on the Job Interval you set while scheduling them. If the models selected in the job have not changed between job intervals, the job still runs according to the schedule. However, no data is exported to erwin DI.

## Case IV: New Model in the Folder

If a new model is added to an existing folder on which a recurring job has been scheduled, DM Connect for DI auto-syncs it to the job. The new model in included in the job automatically, when the job runs next.

## Scenario: Schedule Jobs to Import Data Models from erwin DI to erwin DM

An Import to DM job imports environments and the underlying tables, columns, and metadata to a mart catalog in the original file format as a model. You can then, connect to your mart via erwin DMand open the saved model. erwin DMautomatically converts this model to an erwin model. You can save this model locally or on mart. When you save this model back to the mart, it is saved with the corresponding timestamp.


For more information about data sharing between erwin Data Modeler (erwin DM) and erwin Data Intelligence (erwin DI), refer to the Data Sharing topic.

By default the DM Connect for DI app opens in the Calendar view. You can toggle the page view between the List View ( ) or Calendar View ( ) using the respective buttons on the page toolbar.

To schedule import to DM jobs, follow these steps:

- 1. In the header pane, click and then click **DM Connect for DI**. The DM Connect for DI page opens.
- 2. Click a suitable calendar slot or click Import Job.
- 3. Click **Import to DM**.

The Add Import Job page appears.



#### 4. Set up job parameters as follows:

Tab	Field	Description
DI Inform- ation	Connectors	Select a configuration to use for the import job.
	Systems Name	Select a system from the list of available systems based on your DI configuration
	Environment Name	Select one or more environments from the list of available environments based on the selected system.
Library	Select Models	Select the mart catalog/library to import models to.


Scenario: Schedule Jobs to Import Data Models from erwin DI to erwin DM

Tab	Field	Description
Job Information	Job Name	Specify a job name.
	Start Date/Time	Select the date and time at which the job must run.
	Job Interval	Select a suitable frequency at which the job must run. You can set the job to run once or recur daily, weekly, monthly, or yearly. You can also set up custom recurrence for jobs.
	Frequency	Select the hourly frequency at which the job should run.
		This property is available only when you set the Job Interval to Recurring.
	End Date/Time	If you set up recurring jobs, select the date and time at which the recurrence must end.
	Days	Select the days of the week on which the job should run. The days available here depend on the End Date/Time.
		This property is available only when you set the Job Interval to Recurring.
	Notify Me	Select whether a notification is sent to you when the job status changes. This enables the Notification Email and CC List fields.
	Notification Email	Specify the email address at which you want to receive the notification.
	CC List	Specify a semi-colon-separated list of email addresses that must receive the job notification.
	Run Now	Select the check box to run the job immediately.

#### 5. Click Save.


The job is added to the calendar with its **Job State** set to Scheduled.

On successful job completion, the imported model is added to the selected library in the original erwin DI format. To use this model, you must convert it to erwin DM format.




To convert an imported model to erwin DM format, follow these steps:


- 1. Start erwin DM and connect to your mart.
- 2. On the ribbon, click **Mart** > **Open**.




3. Select the required model and click Open. The process to convert the imported model to the erwin DM format runs.



Once this process is complete, the model is converted to .erwin format and opened in the diagram editor.



This model is saved to your mart catalog in the .erwin format with a time stamp. The following image shows the saved model in the Catalog Manager and in your mart library.




# Scenario: Export Logical Names from erwin DM to erwin DI

An Export BGM job converts logical names to an erwin DI-compatible format and exports them to the Business Glossary Manager as Business Terms.

For more information about data sharing between erwin Data Modeler (erwin DM) and erwin Data Intelligence(erwin DI), refer to the Data Sharing topic.


To schedule logical name export jobs, follow these steps:

1. In the header pane, click and then click **DM Connect for DI**. The DM Connect for DI page opens.



2. Click Export Logical Names Job.

The Add Export BGM Job page appears.



### 3. Set up job parameters as follows:

Tab	Field	Description
		Select models from catalog to export.
Catalogs	Catalog Tree	Before you select models, you can use the All Catalogs or Loaded Catalogs to display all available catalogs or only the expanded catalogs respectively.  Apart from that, after you select catalogs, you can click to view only the selected catalogs in the Catalogs section.
	Include NSM	Select whether naming standards must be exported. A catalog named by NSM file is created under <b>Business Glossary Manager</b> > <b>DM NSM Files</b> custom

### Scenario: Export Logical Names from erwin DM to erwin DI


Tab	Field	Description
		asset.
		Ensure that the DM NSM Files asset is available in the Business Glossary Manager.
DI Inform- ation	Connectors	Select a configuration to use for the export job.

Tab	Field	Description
	Job Name	Specify a job name.
	Start Date/Time	Select the date and time at which the job must start.
	Job Interval	Select a suitable frequency at which the job must run. You can set the job to run once or recur daily, weekly, monthly, or yearly. You can also set up custom recurrence for jobs.
	Frequency	Select the hourly frequency at which the job should run.
		This property is available only when you set the Job Interval to Recurring.
	End Date/Time	If you set up recurring jobs, select the date and time at which the recurrence must end.
Job Information	Days	Select the days of the week on which the job should run. The days available here depend on the End Date/Time.
		This property is available only when you set the Job Interval to Recurring.
	Notify Me	Select the check box to receive a notification when the job status changes. This enables the Notification Email and CC List fields.
	Notification Email	Specify the email address at which you want to receive the notification.
	CC List	Specify a semi-colon-separated list of email addresses that must receive the job notification.
	Run Now	Select the check box to run the job immediately.

### 4. Click Save.


The job is added to the calendar with its **Job State** set to Scheduled.

The job runs according to the schedule and exports logical names to Business Glossary Manager. For example, the logical names, Customer and Customer Credit, from the eMovies model are saved as business terms in the Business Glossary Manager.




# Scenario: Import Source and Target Data into Mapping Manager

In case of dimensional model that has associated data sources, DM Connect for DI exports the source and target column data from the model into the Mapping Manager.



Schedule a job on your dimensional model. Once the job is completed successfully, DM Connect for DI creates a project. Under this project, it creates a mapping specification with the source and target column data from your model.


#### Scenario: Import Source and Target Data into Mapping Manager



### Scenario: NSM Files

If the models selected in a job have NSM files associated with them, DM connect for DI exports them to the Business Glossary Manager under the custom asset, DM NSM Files.


Ensure that the erwin DM NSM asset is enabled under erwin DI's Application Menu > Settings > Business Glossary Manager & Data Marketplace.



The NSM assets are available under the DM NSM Files tab on the Business Glossary Manager.

The screenshot below displays the synced NSM files added as catalogs from erwin DM.

#### Scenario: NSM Files



## Case I: One NSM File, Multiple Models

In a job, if a single NSM file is associated with multiple models, a single catalog is created for both models. The contents of the corresponding catalog under the erwin DM NSM asset type in Business Glossary Manager are overwritten.


## Case II: Multiple NSM Files, Multiple Models

In a job, if multiple NSM files are associated with multiple models, multiple catalogs, corresponding to the NSM files are created under the erwin DM NSM asset type in Business Glossary Manager.

## Scenario: View Logs

After a job runs, you can view its log to understand more about the job status. In case of failures, you can then troubleshoot using the logs.

To view a job's log, select a job and click View Log.



# Reference: Data Sharing between erwin DM and erwin DI

For data to be shared between erwin Data Modeler and erwin DI, the attributes and properties of objects in both the applications must correspond to each other. Refer to the following tables to understand how erwin DM Connect for DI maps data between applications.

LIBRARY-SYSTEM		
erwin Data Modeler	erwin DI	
Library/Catalog Name	System Name	
Description	Business Purpose	

MODEL-ENVIRONMENT		
erwin Data Modeler	erwin DI	
Model Name	System Environment Name	
Model Type	System Environment Type	
Version	Version	
Description	Intended Use Description	

TABLE-TABLE	
erwin Data Modeler	erwin DI
Model Name	Environment Name
Library Name	System Name
Entity Name	Logical Table Name
Comment	Table Comments
Schema_Name	Schema

COLUMN-COLUMN	
erwin Data Modeler	erwin DI
Domain Parent	Data Domain
Physical Data Type	Data Type, Precision, Length, Scale
Null Option	Nullable Flag
Foreign Key	Foreign Key Flag
Primary Key	Primary Key Flag
Child Column Name	Foreign Key Column Name
Child Table Name	Foreign Key Table Name

UDP-EXTENDED PROPERTIES	
erwin Data Modeler	erwin DI
UDP Name	Key Name
Value	Value
Description	Description

NSM-DM NSM FILES		
erwin Data Modeler	erwin DI	
NSM File Name	Catalog Name	
Abbreviation	Asset Name	
Glossary Word	Definition	

NSM files have multiple parameters. However, DM Connect for DI is configured to push only the Glossary Word and Abbreviation to erwin DI.

LOGICAL NAMES-BUSINESS TERMS	
erwin Data Modeler	erwin DI
Logical Tables/Columns	Business Terms
Table/Column Definitions	Business Term Definitions

DATA MOVEMENT SOURCE-MAPPING		
erwin Data Modeler	erwin DI	
Data Source DBMS Type	Database Type	
DS Transformations	Business Rule	
Library	Target System	
Model	Target Environment	
Table	Target Table	
Column	Target Column	
Datatype and Length	Target Column Datatype and length	
Source Library (Or Data Source Name)	Source System	
Source Model (Or Data Source Server)	Source Environment	
Source Table (Or Data Movement Table)	Source Table	
Source Column (Or Data Movement Column)	Source Column	
	Source Column Datatype and length	
Source Column Datatype (Or Data Movement Column Data- type)	Check whether datatype and length are added to the corresponding fields. If not, you need to correct it manually.	

## Limitations

The following list summarizes the limitations of erwin DM Connect for DI.

- If table's or column's Definition property is updated in a model, the update is not exported when the job is run again. To export the updated Definition, set the job's Export Options to Delete & Reload.
- When you apply an NSM file to a model, it is applied at the model-level. Therefore, it is applied to all versions of the model.
- When you use the validation rules, enure that the names of valid values do not exceed 200 characters, or the validation rules are not exported to DI.